

Jacket-Shirt - Sewing Pattern #2665

Recommendations on fabric: natural/mixed soft suiting fabrics and corduroy in two matching colors.

You will also need: fusible interfacing; 9 buttons.

Seam allowances: Seam allowance for hem of garment - 2 cm, seam allowance along upper edge of pocket - 2 cm, other seams - 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Front right - cut 1
3. Front yoke - cut 2
4. Sleeve - cut 2
5. Collar - cut 2
6. Cuff - cut 2

7. Center front facing – cut 2
8. Back neck facing – cut 1
9. Pocket – cut 2
10. Flap – cut 4

Main fabric 1:

1. Front left- cut 1
2. Back yoke – cut 1

Fusible interfacing:

1. Center front facing – cut 2
2. Collar – cut 1
3. Cuff – cut 2
4. Back neck facing – cut 1
5. Flap – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew back yoke to yoke. Serge and press towards top.
3. Pin the pocket flaps together pairwise, right sides together and sew side and lower edges. Trim seam allowances, turn right side out and press.
4. Serge the upper edge of pocket. Fold the seam allowance inside and topstitch. Fold the side edges and the lower edges of the pockets inside and press. Pin pocket onto front and topstitch according to markings.
5. Sew front yoke to front, inserting flap. Serge seams and press towards top.
6. Sew side and shoulder seams, press towards the back and serge.
7. Pin upper collar to lower collar, right sides together. Sew ends of collar and collar fall. Trim seam allowances. Turn the collar right side out, straighten and press.
8. Sew shoulder seams of back neckline facing and center front facings. Press the seam apart. Serge outer edges.
9. Pin center front facing and facing onto the right side of the main piece, baste together along the seams and sew center front facings and neckline, inserting collar. Fold center front facing and facing onto wrong side and press the center front edges. Baste together along the shoulder edges center front facings and top of garment.
10. Cut slit on sleeve along the marked line. Cut bias tape from main fabric (or take ready), its width should

equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew bias tape to slit of sleeve (pin bias tape to slit edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line).

11. Sew sleeve seam, press towards the back and serge.

12. Fold cuffs in half lengthwise right sides together and sew side edges and corner. Start and stop stitching exactly at the marked line of the cuff seam. Turn the piece right side out, press. Sew the outer part of the cuff to the sleeve, fold inside the inner side of the cuff, and topstitch into the seam of the outer cuff cuffs.

Sew sleeves into armholes, serge and press. Sew a gathering stitch along lower edge of sleeve and gather fullness.

13. Serge the lower edge of garment, turn inside and topstitch.

14. Make button holes on the right front, on the cuffs, and on the pocket flaps. Sew on buttons onto left front, pockets and cuffs.

TECHNICAL DRAWING:

