

## Coat With One-Piece Collar - Sewing Pattern #2667

Recommendations on fabric: thin natural/mixed fabric suitable for coats.

You will also need: lining; fusible interfacing; 2 buttons; shoulder pads.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve - 3.0 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Lower back - cut 2
4. Center front - cut 2
5. Side front - cut 2
6. Lower front - cut 2

7. Upper sleeve - cut 2
8. Lower sleeve - cut 2
9. Center front facing - cut 2
10. Back neck facing - cut 1

Lining:

1. Center back - cut 2
2. Side back - cut 2
3. Lower back - cut 2
4. Center front - cut 2
5. Side front - cut 2
6. Lower front - cut 2
7. Upper sleeve - cut 2
8. Lower sleeve - cut 2

Fusible interfacing:

1. Center front facing - cut 2
2. Back neck facing - cut 1
3. Upper front - cut 2

Attention! Lining is cut using the pattern pieces for main fabric, except for the width of the center front facing and the back neckline facing.

## **INSTRUCTIONS:**

1. Apply fusible interfacing.
2. Sew center back seam on lower back pieces and upper back pieces, press the seam apart. Sew side backs to center back. Press the seam apart. Sew upper back to lower back. Press the seam apart.
3. Sew side front to front. Press the seam apart. Sew upper front to lower front. Press the seam apart.
4. Sew shoulder and side seams, press the seam apart.
5. Sew center edge of one-piece collar. Sew one-piece collar into neckline, clipping into seam allowance near corner.
6. Sew shoulder edges of center front facings and back neckline facing, press the seam apart. Sew center collar seam. Sew the collar into the facing's neckline, clipping into seam allowance near corner. Pin center front facing onto main piece, right sides together, pin together and sew center front edge, lapels, collar and lower edge. When stitching make sure to place the front piece on top. Topstitch seam allowance of the central front facing onto the central front facing. Place stitch line at 0,2 cm from seam. Turn center front facing onto wrong side, straighten, press.

7. Sew on shoulder pads.
8. Sew elbow seam on sleeve, press the seam apart. Press the lower seam allowance of the sleeve onto wrong side. Sew front seam on sleeve, press seam allowances towards lower part. Sew sleeves into armholes matching notches, press seam.
9. Fold under seam allowance along hem and press.
10. Sew seams on lining, leaving an opening in left elbow seam of sleeve. Sew lining to back facing and to center front facing. Sew lining to lower edge of garment and lower edge of sleeve. Turn the garment right side out through the opening. Sew the opening closed.
11. Make buttonholes on right front, sew on buttons onto left front.

## **TECHNICAL DRAWING:**

