

Blouse With Decorative Sleeves - Sewing Pattern #2791

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 7 buttons.

Seam allowances: Seam allowance for hem of garment - 2 cm; other seams - 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Back yoke - cut 1
3. Front - cut 2
4. Sleeve - cut 2
5. Collar — cut 2
6. Stand collar - cut 2
7. Sleeve lining - cut 2

Fusible interfacing:

1. Collar — cut 1
2. Stand collar - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing. Apply fusible interfacing to the one-piece placket on the front.
2. Sew darts on front, press bulk towards top.
3. Sew yoke to back. Serge seams and press towards top. Sew a decorative stitch along the yoke edge at 0.5 cm from seam.
4. Fold the longer seam allowances of the placket onto the wrong side and press. Fold the one-piece front onto the wrong side and topstitch along the marked lines.
5. Sew shoulder and side seams, press towards the back and serge.
6. Pin upper collar to lower collar, right sides together, sew ends of collar and collar fall. Trim seam allowances, turn the collar right side out, straighten and press. Pin stand collars together, right sides together, put ready collar between them, adjust notches and sew, sewing ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press. Sew upper stand collar with collar into neckline, fold raw edge of lower stand collar and stitch-in-the-ditch along seam of upper stand collar.
7. Make and baste pleats on sleeves. Sew the lining to the lower edge. Baste together the sleeve cap edges of the main fabric and the lining. Sew sleeve into armhole. Serge and press.
8. Turn hem under inside at 1 cm, then again at 1 cm and topstitch.
9. Make buttonholes on right front, sew on buttons on the left one. Make buttonholes and sew on buttons on the stand collar.

TECHNICAL DRAWING:

