

## Denim Shirt - Sewing Pattern #2787

Recommendations on fabric: natural/mixed jeans fabrics.

You will also need: fusible interfacing; 10 push buttons.

Seam allowances: Seam allowance for hem of garment - 2 cm;  
other seams - 1 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back - cut 1 on fold
2. Back yoke - cut 1 on fold
3. Front - cut 2
4. Front yoke - cut 2
5. Sleeve - cut 2
6. Pocket - cut 2
7. Collar — cut 2

8. Stand collar - cut 2
9. Cuff - cut 2
10. Placket - cut 2

Fusible interfacing:

1. Collar — cut 1
2. Stand collar - cut 1
3. Cuff - cut 2
4. Placket - cut 2

## **INSTRUCTIONS:**

1. Apply fusible interfacing.
2. Sew yoke to back, slash the back piece in the corner. Serge seams and press towards top. Sew a decorative stitch at 0.5 cm from seam.
3. Serge the upper edge of pocket, fold under the seam allowance and topstitch. Fold inside side and lower seam allowances of pocket onto wrong side and press. Pin pocket onto front and topstitch according to markings.
4. Sew yoke to front. Serge seams and press towards top. Sew a decorative stitch at 0.5 cm from seam.
5. Sew shoulder seams, press towards the back and serge.
6. Install the upper parts of the push buttons onto the right placket. Pin the right placket onto the right front right sides together and sew center front edge. Fold the placket onto wrong side, fold inside the seam allowance of the inner side and topstitch from the right side. Pin the left placket onto the left front right sides together and sew center front edge. Fold the placket onto wrong side, fold inside the seam allowance of the inner side and topstitch from the right side.
7. Pin upper collar to lower collar, right sides together, sew ends of collar and collar fall. Trim seam allowances, turn the collar right side out, straighten and press. Sew a decorative stitch along the collar ends and the collar outer edge of collar. Pin stand collars together, right sides together, put ready collar between them, adjust notches and sew, sewing ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press. Sew upper stand collar with collar into neckline, fold raw edge of lower stand collar and stitch-in-the-ditch along seam of upper stand collar.
8. Cut slit on sleeve along the marked line. Cut bias tape from main fabric (or take ready), its width should equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew bias tape to slit of sleeve (pin bias tape to slit edge from the right

side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line). Make and baste pleats on sleeves. The bulk is directed away from closure.

9. Sew sleeves into armholes, serge and press.

10. Sew side seams and sleeve seams. Serge seams and press towards back.

11. Fold cuffs in half lengthwise right sides together and sew the side edges and the corner. Start and stop stitching exactly at the marked line of the cuff seam. Snip into seam allowance near the notch. Turn the piece right side out, press. Sew the outer part of the cuff to the sleeve, fold inside the inner side of the cuff, and topstitch into the seam of the outer cuff cuffs. Sew a decorative stitch around all edges cuffs.

12. Turn hem under inside at 1 cm, then again at 1 cm and topstitch.

12. On left front install the push buttons. Install push buttons on the cuffs and on the stand collar.

## **TECHNICAL DRAWING:**

