

Asymmetrical Knit Top - Sewing Pattern #2848

Recommendations on fabric: soft natural/mixed knit fabric of medium stretchiness.

Seam allowances: all seams - 1.0 cm; seam allowance for hem of garment and hem of sleeve - 2 cm; seam allowance of the vertical edge of the lower front - 2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 - 0.8 cm.

CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Attention! Pattern blocks have markings and texts from the right side. Take this into account when cutting the fabric-some of the pattern blocks need to be laid onto fabric with their wrong side on top!

Main fabric:

1. Back - cut 1 on fold



2. Right front - cut 1
3. Left front - cut 1
4. Lower front - cut 1
5. Sleeve - cut 2
6. Neckline facing - cut 1

INSTRUCTIONS:

1. Sew center front seam, press towards left, serge. Make and baste box pleats.
2. Serge the vertical edge and the lower edge of lower front, press onto wrong side and topstitch. Serge the lower edge and the lower shaped edge of the front, press onto wrong side and topstitch.
3. Pin the front, wrong side down, onto the right side of the lower front. Sew the horizontal seam of the inset, serge and press. Front straighten, baste together along side edge.
4. Sew shoulder and side seams, press towards the back and serge.
5. Sew neckline facing into a ring, pin together in half lengthwise and sew into neckline, slightly stretching the facing. The seam is located near the left shoulder seam. Serge the seam allowances and press towards the main piece.
6. Sew sleeve seam, press towards the back and serge. Sew sleeves into armholes, matching notches, serge and press.
7. Serge the seam allowance for hem of back and hem of sleeve, press onto wrong side and topstitch.

TECHNICAL DRAWING:

