

Sweatshirt With Hood - Sewing Pattern #2867

Recommendations on fabric: natural/mixed knit fabric of small/medium stretchiness in contrasting or similar color (footer).

You will also need: fusible interfacing; 3 buttons.

Seam allowances: all seams 1 cm; Upper seam allowance of pocket - 2 cm; seam allowance for hem of garment - 1.5 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 - 0.8 cm.

CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Center front - cut 1 on fold
3. Center sleeve - cut 2



4. Pocket - cut 2
5. Hood - cut 2
6. Cuff - cut 2

Main fabric 1:

1. Side front - cut 2
2. Front sleeve - cut 2
3. Back sleeve - cut 2

Fusible interfacing:

1. Placket - cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Serge the upper edge of pocket. Press the seam allowance onto wrong side and topstitch; fold inside the open edges and press onto wrong side. Place the pocket onto the side front according to the markings and topstitch.
3. Sew side fronts to front, press seam allowances towards center, serge.
4. Press plackets in half lengthwise right side out. Pin plackets onto right side front and sew. Make diagonal slashes in corners on front. Fold away plackets onto wrong side and straighten. Pin right placket onto left placket, fix the lower corner with double stitch line from the wrong side. Serge and press. Make buttonholes and sew on buttons on placket.
5. Sew side and shoulder seams, press towards the back and serge.
6. Pin hoods together right sides together and sew. Serge the seam allowances and press towards left. Serge the outer edge. Fold under the seam allowance and topstitch. Sew hood into neckline, serge and press.
7. Sew the sleeve seams, press towards center and serge. Sew sleeve seam, press towards back and serge. Sew cuff into a ring. Press the seam apart. Fold cuff in half lengthwise and press. Sew cuff to lower edge of sleeve, slightly stretching it. Serge and press.
8. Sew sleeves into armholes, serge and press.
9. Serge bottom edge of garment, press onto wrong side and topstitch.

TECHNICAL DRAWING:

