

## Dress With Stand Collar - Sewing Pattern #2899

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; dress zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of dress and hem of sleeve — 2 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back - cut 2
2. Front - cut 1 on fold
3. Sleeve - cut 2
4. Stand collar - cut 2
5. Front neck facing — cut 1

Fusible interfacing:

1. Front neck facing — cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing.
2. Sew darts on back. Press bulk towards center.
3. Serge the center back edges separately. Sew center back seam from top to zipper marking and from the lower marking down to hem, press the seam apart. Sew in zipper.
4. Sew darts on front. Press bulk of bust darts towards top, press bulk of waist darts towards center.
5. Cut (or take ready) bias tape , its width should equal 4 cm and its length should equal 90-100 cm. Fold bias tape in half lengthwise right side out and press, fold the longer edges towards the center and press. Sew a decorative stitch. Cut into two equal parts.
6. Serge the outer edge of the front neckline. Place the front neckline facing and the front right sides together and sew the neckline cutout, inserting the decorative cord. Trim away corners and clip into curves, turn pieces right side out, straighten, press. Sew a decorative securing stitch along the neckline cutout. Secure the seam allowances of the neckline and the facing together. Treat as one piece in the future.
7. Sew shoulder and side seams, press towards the back and serge.
8. Pin together parts of stand collar, right sides together and sew upper and side edges, start and stop stitching exactly at the marked seam line. Clip into curves, trim away corners, turn stand collar right side out and press.
9. Sew the outer stand collar into the back neckline and into the front neckline, press seam allowances towards stand collar. Fold under the seam allowance of the inner stand collar and topstitch into the seam of the outer stand collar.
10. Slipstitch facing to garment along the shoulder seam and the zipper tape.
11. Sew sleeve seam, serge seams and press towards back. Sew sleeves into armholes. Serge and press.
12. Serge lower edge of garment and lower edge of sleeve, press onto wrong side and topstitch.

## **TECHNICAL DRAWING:**

