

Sewing Pattern — Shirt 4269

Recommended fabric: natural / mixed blouse fabric (cotton, viscose, polyester).

You will also need: fusible interfacing, trim (approximate length is mentioned on front part pattern), 12 buttons

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: hem of the garment and hem of sleeve – 1.5 cm, all other seams – 1 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.

CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Back - cut 2
2. Front - cut 2
3. Front inset -cut 2
4. Sleeve –cut 2
5. Collar – cut 2
6. Collar-stand – cut 2
7. Sleeve strap– cut 2
8. Placket - cut 2



Fusible interfacing:

1. Outer collar – cut 1
2. Inner collar-stand – cut 1
3. Placket – cut 2
4. Sleeve strap – cut 2

INSTRUCTIONS:

1. Apply fusing to outer collar, inner collar-stand, plackets, sleeve straps.
2. Place outer collar and inner collar, right sides together. Sew ends and outer edge of collar. Trim corners. Turn collar out, straighten and press. Place collar-stands, right sides together, insert collar between them, match notches and sew, include ends of collar-stand at the same time. Start and finish the stitch exactly near marked line of collar-stand connecting seam. Turn collar out and press.
3. Sew darts on front parts. Press toward hem. Sew darts on back part. Press darts toward center. Sew center seam of back. Finish or serge and press seam allowances toward left.
4. Topstitch trim onto front inset according to marking. Make and baste pleats on front inset (folds are pressed towards center). Sew front inset to front, trim corners. Finish or serge seam and press toward inset.
5. Press plackets in half lengthwise wrong sides together. Sew raw edges of plackets to front part, press seams toward placket. Turn the edge of inner placket inside and topstitch into connecting seam.
6. Sew shoulder seams. Finish or serge seam and press toward back.
7. Sew outer collar-stand with the collar into the neckline, turn up seam allowance of inner collar-stand and topstitch into outer collar-stand connecting seam. Topstitch along collar-stand and collar at 0.1 cm off the edge.
8. Fold sleeve strap right sides together and sew long and short sides. Trim seam allowances in corners, turn right side out and press. Make a buttonhole. Sew the strap from the wrong side of sleeve according to markers. Sew a button at mark on right side.
9. Sew sleeve into open armhole, finish or serge and press seam allowance.
10. Sew edge of sleeve and side edge with one seam, finish or serge seam and press toward back.
11. Serge hem of the garment and of sleeve, press under and topstitch.
12. Make buttonholes on right front, sew buttons on left front.

TECHNICAL DRAWING:

