

2906 - Sewing Pattern #2906

Recommendations on fabric: soft natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing, 3 outer buttons, 8 flat buttons for hidden placket.

Seam allowances: seam allowance for hem of garment — 2.0 cm, other seams 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Upper back – cut 2
2. Center back — cut 1
3. Lower back — cut 1 on fold
4. Upper right front — cut 1
5. Upper left front — cut 1
6. middle front — cut 2
7. Lower front — cut 2

8. Back armhole facing — cut 4
9. Front armhole facing — cut 4
10. Back neck facing - cut 1
11. Front neck facing — cut 2
12. Concealed placket of the lower part - cut 1

Fusible interfacing:

1. Back armhole facing — cut 2
2. Front armhole facing — cut 2
3. Back neck facing - cut 1
4. Front neck facing — cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on upper backs, press the inner part towards center. Sew center seam on upper back, press seam allowances towards left, serge.
3. Finishing the right front edge. Fold the right upper front part right sides together along the line “kray borta” (front edge). Sew the upper corner between the lines “kray borta” (front edge) and “vnutrenniy kray planki” (inner edge of the placket). Fold the right upper front part right sides together along the line “kray borta potaynoy planki” (front edge of the concealed placket). Sew the upper corner between the lines “kray borta potaynoy planki” (front edge of the concealed placket) and “vnutrenniy kray planki” (inner edge of the placket)..
4. Sew shoulder seams, press seam allowances towards back, serge.
5. Sew the shoulder edges of the neckline facings and press the seam allowances open. Serge the outer edge. Sew the front neckline facings to the inner edges of the integrated plackets and serge the seam allowances. Place the neckline facings and the main garment right sides together, folding the fronts along the line “kray borta” (front edge), and sew the neckline edge. Clip the seam allowances on the curves. Turn the pieces right side out, shape the corners of the plackets, and press. Make buttonholes on the inner placket of the concealed fastening.
6. Sew the shoulder seams of the armhole facings, press the seam apart. Pin pieces together of facings right sides together and sew the outer edge. Clip into curves, turn pieces right side out, straighten, press.
7. Place the facings on the wrong side of the garment and sew the armhole edges. Clip into curves, press and serge. Turn right side out facings onto right side, straighten, press. Secure to the main garment along the side edges.
8. Sew side seams on the upper part of garment, press the seam apart, serge. Sew a gathering stitch along the

lower edge of upper front and gather fullness.

9. Sew the side edges of the middle part of the garment, press the seam allowances toward the back, and serge them. Serge the edges of the integrated plackets. Sew the middle part to the upper part, wrapping the upper part with the integrated placket of the middle part. Press the seam allowances downward and serge them. Turn the placket to the wrong side.

10. Sew the concealed placket to the lower right front part and serge the seam allowances up to the lower edge. Serge the edge of the integrated placket on the lower left front part.

Finishing the front edge of the lower right front part. Press the placket to the wrong side along the line “kray borta potaynoy planki” (front edge of the concealed placket). Make the buttonholes. Press the placket along the line “kray borta” (front edge), aligning it with the line “kray borta potaynoy planki” (front edge of the concealed placket).

Finishing the front edge of the lower left front part. Press the integrated placket to the wrong side along the line “kray borta” (front edge).

11. Sew side edges on lower part of the main piece, press seam allowances towards back, serge. Sew the lower part to the middle part, wrapping the lower part with the integrated placket of the middle part. Press towards top and serge. Turn placket onto wrong side.

12. Sew a decorative securing stitch along the front edge at the width of the placket.

13. Serge the lower edge of garment, press onto wrong side and topstitch.

14. Make buttonholes on the right middle front part. Sew on buttons correspondingly. Sew on the buttons of the concealed placket.

TECHNICAL DRAWING:

