

Blouse With A Peplum - Sewing Pattern #2936

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing, 5 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem of garment – 1.5 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Upper center back - cut 2
2. Upper side back - cut 2
3. Lower back - cut 1 on fold
4. Upper center front - cut 2
5. Upper side front - cut 2
6. Lower front - cut 1 on fold
7. Center front facing - cut 2

- 8. Back neck facing — cut 1
- 9. Sleeve — cut 2
- 10. Cuff — cut 2

Fusible interfacing:

- 1. Center front facing - cut 2
- 2. Back neck facing — cut 1
- 3. Cuff — cut 2

INSTRUCTIONS:

- 1. Apply fusible interfacing.
- 2. Sew the center back seam, press towards left, serge. Sew side backs to center back, press seam allowances towards center, serge.
- 3. Sew side front to center front, press seam allowances towards center, serge.
- 4. Sew shoulder seams, press seam allowances towards back, serge.
- 5. Sew shoulder edges of center front facings and back neckline facing, press the seam apart. Serge the outer edge. Pin center front facings onto garment right sides together and sew the back neckline and the center front edges. Clip into curves, trim away corners, turn the center front facings onto wrong side, straighten, press. Put right front onto left front and baste together along lower edge.
- 6. Sew a gathering stitch along the upper edge of lower back and gather fullness. Sew upper back to lower back, press seam allowances towards top, serge.
- 7. Sew a gathering stitch along the upper edge of lower front and gather fullness. Sew upper front to lower front, press seam allowances towards top, serge.
- 8. Sew side seams, press seam allowances towards back and serge.
- 9. Sew sleeve seam, serge and press. Sew a gathering stitch along the sleeve cap and gather fullness. Sew sleeves into armholes, serge and press.
- 10. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise right side out and press. Sew the outer cuff to the lower edge of the sleeve, press the seam allowances towards cuff. Turn under seam allowance of inner cuff and topstitch into seam of.
- 11. Serge hem of garment, press onto wrong side and topstitch.
- 12. Make buttonholes on right front, sew on buttons on the left one.

TECHNICAL DRAWING:

