

Sewing Pattern — Dress 8000

Recommendations on fabric: natural or blended dress fabric

You will also need: invisible zipper, fusible interfacing

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

SEAM ALLOWANCE: All seams - 1 cm, hem of the garment - 3 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Fabric:

1. Back bodice - cut 2
2. Front bodice - cut 1 on fold
2. Back skirt - cut 2
4. Front skirt - cut 1 on fold
5. Back neckline facing – cut 2, cut 2 of interfacing
6. Front neckline facing – cut 1, cut 1 of interfacing
7. Back armhole facing – cut 2, cut 2 of interfacing
8. Front armhole facing - cut 2, cut 2 of interfacing

INSTRUCTIONS:

1. Apply interfacing to all facings.
2. Sew waist darts on bodice front according to markers. Press darts towards center. 3. Sew darts on bodice back. Press darts towards center.
4. Stitch skirt backs to bodice backs. Serge seam edge and press toward skirt.
5. Stitch front skirt to front bodice. Serge seam edge and press toward skirt.
6. Sew center seam of back section from the «zipper» notch up to hem. Press seam allowances open. Press opening for zipper. Serge edges.
7. Sew in invisible zipper according to zipper installation instructions.
8. Sew shoulder seams and side seams. Serge edges and press seam allowances towards back.
9. Sew front and back neck facings together at side seams, press seam allowances

open. Serge outer edges.

10. Sew the neck facing to the neckline of bodice, right sides together. Trim and clip into seam allowance for ease. Press seam up toward facing. Turn facing to inside, Press. Slip-stitch center edges of the facing to zipper allowance. Tack facing to shoulder seams. Topstitch around neckline if desired.

11. Sew front and back armhole facings together, press seams open. Serge outer edges.

12. With right sides together, sew armhole facings to armholes, matching seams and notches. Trim and clip into seam allowance for ease. Press seam toward facing. Turn facing to inside, tack at shoulder seam and side seam. Topstitch around armhole if desired.

13. Turn under hem, press. Topstitch or hem by hand.

TECHNICAL DRAWING:

