

Sewing Pattern — Dress 4264

Recommendations on fabric: fabric suitable for dresses, two other fabrics for border trims.

You will also need: fusible interfacing, invisible zipper, decorative belt buckle of 8 cm high, eyelets.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: hem of the dress – 4 cm; other seam allowances – 1 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric 1:

1. Upper back - cut 1
2. Lower back skirt - cut 1 on fold
3. Inset of back_2 - cut 1 (*vstavka)
4. Upper front – cut 2
5. Lower front skirt - cut 1 on fold
6. Inset of front_2 - cut 1 (*vstavka)
7. Back neck/armhole facing - cut 1
8. Front neck/armhole facing - cut 2
9. Belt - cut 1 (*waistband)



Border Trim Fabric - 1:

1. Inset of back _1 - cut 1 (*vstavka)
2. Inset of front _1 - cut 1 (*vstavka)

Border Trim Fabric - 2:

1. Inset of back _3 - cut 1 (*vstavka)
2. Inset of front _3 - cut 1 (*vstavka)

Fusible Interfacing:

1. Back neck/armhole facing - cut 1
2. Front neck/armhole facing- cut 1

INSTRUCTIONS:

1. Apply interfacing to facings.
2. Sew waist darts on upper back, cut depths up to 1 cm, serge and press towards center. Sew darts on front at 3 cm from lower edge, press the depth open.
3. Sew center front seam, serge and press seam allowances open.
4. Make and baste pleats on lower back, depths are directed towards center. Sew upper and lower back, serge and press seam allowances upwards. Sew inset_1 to lower back, press seam allowances upwards and serge. Sew inset_2 to inset_1, serge and press seam allowances upwards. Sew inset_3 to inset_2, serge and press seam allowances upwards. Construct front section in the same way.
5. Serge left side edges separately. Sew left side seam from the armhole down to the first notch and from the second notch down to hem, press seam allowances apart, including opening for zipper. Sew in zipper. Sew right side seam, serge and press seam toward back.
6. Sew center seam of front facing, starting the stitch exactly near marked neckline, press seam allowances apart. Sew front and back facings at side seams, press seam allowances apart. Serge lower edge. Pin the facing to the neckline, right sides together. Sew the neckline and the armhole, clip into curves. Turn right side out, and press.
7. Sewing front and back shoulder seams: Turn the edges of back shoulder opening to the inside of the opening. Funnel the front shoulder edges inside the back shoulder opening. Put your hand between the facing and the garment and grab the shoulder edges and pull them through. Line up seams, pin and sew. Here is an excellent video on how to sew this type facing to a garment. <https://www.youtube.com/watch?v=jdiN4Y1bACw> .Turn and press.
8. Serge bottom edge of dress, press onto wrong side, and hem with invisible stitches.
9. Fold belt in half lengthwise, right sides together, and sew on long and one short side. Turn belt right side out, turn seam allowances of unsewn end to the inside and slipstitch closed. Topstitch at 0.5 cm along the perimeter of the belt. Attach the belt buckle. Adjust the length of the belt and apply the eyelets.

TECHNICAL DRAWING:

