

Sewing Pattern — Dress 5882

Recommendations on fabric: light-weight suiting fabric

You will also need: lining, invisible zipper of 45 cm long, fusible interfacing, decorative closure of 6 cm high.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: all seams - 1 cm, on hem of the garment - 3 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Main fabric:

1. Central back – 2 details
2. Side back – 2 details
3. Central upper part of front – 4 details
4. Side upper part of front – 2 details
5. Central lower part of front – 1 detail
6. Side lower part of front – 2 details
7. Waistband – 1 detail
8. Back facing 1 – 2 details
9. Back facing 2 – 2 details

Lining:

1. Central back – 2 details
2. Side back – 2 details
3. Side upper part of front – 2 details
4. Central lower part of front– 1 detail
5. Side lower part of front – 2 details

Interfacing:

1. Central upper part of front – 2 details
2. Back facing 1 – 2 details
3. Back facing 2 – 2 details
4. Waistband – 1 detail

INSTRUCTIONS:

1. Apply interfacing to corresponding details.
2. Sew darts on back. Press darts to center seam.
3. Apply interfacing to wrong side of the vent on both details of central back. Serge center edge of back separately on each detail, serging the vent at the same time. Sew center edge of back from top edge to top mark, from lower mark to the vent edge. Slash away vent's corner on right part. Press apart seam allowances of center seam. Press right side of the vent at 1 cm and topstitch. Press vent seam allowances and fasten with machine stitch. Sew in zipper.
3. Sew princess seams on back, press seam allowances toward center, serge.
4. Sew cord edges of lower parts of front, press seam allowances toward center, serge. Sew cord edges of lower parts of front that is from lining, press seam allowances toward center, serge. Press hem of lining twice onto wrong side and topstitch.
5. Place main fabric and lining details wrong sides together and fasten on top and side edges. Press waistband in half lengthwise, wrong sides together. Serge longitudinal edge of inner sides. Stitch outer side of the waistband to top edge, press seam onto waistband. Topstitch waistband into connecting seam.
6. Stitch unfused central upper part of front to side part. Slash seam allowance and press onto central part. Make and fasten pleats on side part of front.
7. Sew shoulder seams, slash seam allowances on rounded part and press apart.
8. Sew together back facing 1 and back facing 2, press seam allowances apart. Stitch lining of back to facing, press seam onto the facing. Serge seam allowances of center edge. Sew center edge from top up to top mark, from lower mark down to hem. Sew cord edges of back from lining, press seam allowances toward center and serge. Press hem of lining twice onto wrong side and topstitch.
8. Sew fused central upper part of front with lining of side part, slash seam allowance and press on central part.
9. Sew shoulder seams of lining, slash seam allowances on rounded part and press apart.
10. Place lining and main garment right sides together and overstretch the neckline, a part of front edge of front, lower edge of front and armhole edges, ending the stitch exactly near marked line of side seam from back side. Slash seam allowances on rounded parts, turn garment right side out.
11. Put upper part of front onto lower part and fasten on side edge.
12. Insert front between lining and main fabric of back and sew side edges. Serge, press toward back, turn garment right side out.
13. Serge lower edge of the garment, press onto wrong side and undersew with invisible stitches.
14. Set front center edges into closure holes, regulate the length, cut off if needed, serge and topstitch.

TECHNICAL DRAWING:

