

Sewing Pattern — Dress 5851

Recommendations on fabric: natural or mixed fabrics suitable for dresses

You will also need: blind zipper, bias tape, breast-pin

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: along the edge of the dress – 3 cm, along the edge of sleeve 3 cm, all other seams 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Upper front part – 2 details
2. Front yoke – 1 detail
3. Lower front part – 1 detail
4. Back part – 2 details
5. Back yoke – 2 details
6. Lower middle part of the back – 2 details
7. Lower side part of the back – 2 details
8. Front part of sleeve – 2 details
9. Back part of sleeve – 2 details

INSTRUCTIONS:

1. Mark and sew darts on lower front part. Press darts towards center of the front. Mark and sew darts on the back. Press darts towards center of the back. Fold yoke with the back right sides touching and sew edges. Serge and press onto the yoke.
2. Sew lower middle and side parts of the back. Press seam towards center of the back and serge. Stitch lower part of the back to back part yoke. Serge and press onto the yoke. Serge central edges of the back. Sew center seam up to the notch for zipper. Press seam apart, pressing the slit for zipper. Sew in zipper.
3. Sew back part of sleeve into armhole of the back. Serge seam and press towards side of sleeve. Sew upper edge of sleeve. Serge and press towards the back part. Fold bias tape in half

lengthwise wrong sides together and press. Fold the bias tape with neckline edge right sides together and overstretch, turn the bias tape onto wrong side and topstitch along the fold onto main detail. Press the seam.

4. Mark and make pleats along lower edge of upper front part. Direct depths of the darts towards center of the front. Fold details of upper front parts right sides touching and overstretch along top edge.

5. Sew front part of sleeve into armhole of front part, inserting the sleeve between upper front part details. Turn onto right side and press.

6. Fold front yoke with upper front part right sides together and stitch. Serge seam and press onto the yoke.

7. Stitch lower part of the front to front yoke. Serge and press the seam onto the yoke.

8. Sew side seams together with lower edge of sleeve. Serge seams and press towards the back.

9. Press hem of the dress and hem of sleeve onto wrong side, turn inside again at 1 cm and topstitch.

10. Make pleats on upper front part and fasten them with breast-pin.

TECHNICAL DRAWING:

