

Sewing Pattern — Blouse 5804

Recommended fabric: light to medium weight woven fabric

You will also need: fusible interfacing.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: back part and front part neckline edge – 0.7 cm, along the lower edge of the garment and of sleeve – 2 cm, all other seams - 1 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Advice:

Knit fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

Main fabric:

1. Upper back – cut 2
2. Lower back -cut 1
3. Center front – cut 1
4. Side front – cut 2
5. Front inset (waistband) – cut 1
6. Lower front – cut 1 on fold

7. Front neckline facing – cut 1
8. Back neckline facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to back and front neckline facings.
2. Sew center edge of upper back, press seam toward left side and serge.
3. Sew lower back to upper back, press and serge seam allowances.
4. Sew side fronts to center front, press and serge seam allowances.
5. Sew front inset (waistband) to upper part, press seam allowances downwards and serge. Make pleats on lower front part according to markers, stitch lower part to inset (waistband), press seam onto inset and serge.
6. Sew shoulder seams, serge and press toward back.
7. Sew side seams together with lower edges of sleeve, serge and press seam toward back.
8. Sew the neckline facings together. Press open seam allowances; serge outer edge. Pin the facing with the garment right sides together and sew to neckline edge. Clip curves and press seam allowance toward facing. Understitch. Turn facing to wrong side, and slip-stitch at shoulder seams. If desired, topstitch around neckline.
9. Serge seam allowance of lower edge of the garment and of sleeve, press under and topstitch.

TECHNICAL DRAWING:

