

Sewing Pattern — Nightdress 5789

Recommendations on fabric: lace; silk, satin

You will also need: decorative trim; decorative elastic
(approximate length is mentioned on lower back part pattern)

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: all seams -1 cm, top edge of back and sleeve, along the lower edge of sleeve, along center edge of front, along the lower edge of back and of front – 0 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Upper back – cut 1
2. Lower back — cut 1
3. Upper front - cut 2
4. Lower front — cut 2
5. Sleeve - 2 details

Satin:

1. Decoration on back – 1 detail
2. Top decoration of front – 4 details
3. Center decoration of front – 2 details
5. Inner front center decoration – 2 details

INSTRUCTIONS:

1. Sew lower back to upper back. Serge and press seam allowances downwards
2. Make a gathering stitch along the lower edge of upper front between notches at 0.5 cm from the edge and gather fullness. Sew lower front to upper front, serge and press seam allowance downwards.
3. Serge front edge. Topstitch decorative trim onto front edge.
4. Sew top decoration to upper front, press seam allowance onto decoration. Pin lower detail with its right side inwards onto right side of top decoration and sew upper edge, over to the tie, short edge of the tie and lower edge of the tie, up to the notch. Clip into curves and trim corners. Turn the tie onto right side, straighten, press. Turn unsewn lower edge of inner top decoration under and topstitch into decoration connecting seam.
5. Serge top and lower edges of sleeve, as well as top edge of upper back with rolled hem.
6. Sew the sleeve to back, serge and press seam allowances. Sew the sleeve to front, serge and press seam allowances. Sew sleeve seam and side seam with one stitch. Serge and press seam allowances.
7. Mark lower line of connecting the decoration on the garment. Sew side seams of back decoration and center decoration of front. Put decoration onto front part right side onto right side so that connecting line of lower edge of decoration coincides with marked line on the garment. Upper edge of decoration is directed to lower edge of the garment by that. Sew decoration, turn it upwards. Serge one short side of inner front center decoration. Pin inner detail onto front center decoration, right sides together, and sew the tie along three sides. Trim corners. Turn the tie onto right side, straighten, press. Turn unsewn upper edge of the decoration under, and topstitch under connection seam of upper and lower back / front.
8. Topstitch elastic onto upper edge of back part, upper edge of sleeve, and lower edge of sleeve, slightly stretching it. Elastic should be 10% shorter than the edge, onto which it is topstitched.
9. Serge lower edge of garment with narrow rolled hem.

TECHNICAL DRAWING:

