

Sewing Pattern — Nightdress 5782

Recommendations on fabric: lace

You will also need: atlas for decoration

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: allseams -1 cm, hem of the flounce - 0 cm, along tie sides – 0 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 1 detail
2. Front part – 2 details
3. Sleeve – 2 details
4. Flounce – 2 details

The tie:

1. Tie – 6 details.

INSTRUCTIONS:

1. Mark and sew waist darts on back part and bust darts on front part. Press darts on front part upwards, on back part towards center of back part.
2. Cut 3 tapes from atlas of 5.5 cm wide and as long as lower edges of back and front parts. Press one of longitudinal sides of the tape at 1 cm onto wrong side, lay the tape with its right side onto wrong side of back and front parts and overstretch lower edge. Turn the tape onto right side and topstitch pressed edge onto main detail.
3. Sew shoulder seams. Press seam allowances towards back part and serge.
4. Cut bias tape of 5 cm wide and as long as front part / back part neckline. Press bias tape in half lengthwise, wrong sides together. Fold bias tape with neckline seam allowance right sides touching and overstretch. Turn the bias tape onto wrong side. Topstitch seam allowance onto the bias tape with the seam of 0.1 cm wide.
5. Fold ties in half lengthwise, right sides together and overstretch along the long and one short sides. Turn ties onto right side, serge, press and topstitch at 0.1 cm off the edge.

6. Cut 2 tapes from atlas of 5 cm wide and as long as front band. Press them in half lengthwise wrong sides together, lay onto right side of front part and overstretch front band, inserting ties according to markers. Turn the tape onto wrong side and topstitch the fold onto main detail.
7. Serge side edges and sew up to marker slit. Press apart the seam, pressing the slits. Topstitch slit sides at 0.1 cm.
8. Stitch flounce to lower edge of sleeve. Serge the seam and press onto the flounce. Sew and serge sleeve and flounce seam. Serge lower edge of the flounce with thin rolled seam.
9. Sew sleeves into armholes according to notches. Serge.
10. Overstretch two bows that are from atlas fabric and sew them above side slits.

TECHNICAL DRAWING:

