

## Sewing Pattern — Blouse 4249

Recommendations on fabric: natural or mixed fabric suitable for blouses (cotton, viscose, polyester)

You will also need: fusing, 13 buttons.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowances: hem of the garment – 1.5 cm, all other seams – 1cm

**Attention!** First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Main fabric:

1. Back part - 2 details
2. Right front part - 1 detail
3. Left front part - 1 detail
4. Sleeve – 2 details
5. Collar – 2 details
6. Stand-up part of collar – 2 details
7. Cuff – 2 details
8. Placket - 4 details

#### Fusing:

1. Upper collar – 1 detail
2. Lower stand-up collar – 1 detail
3. Placket – 2 details
4. Cuff – 2 details

Attention: placket detail is the same for left and right front parts.

### **INSTRUCTIONS:**

1. Apply fusing to details .
2. Fold upper collar with lower right sides together. Overstitch ends and outer edge of collar. Cut seams off. Turn collar out, straighten and press. Fold stand-up parts of collar right sides together, insert ready collar between them, level notches and sew, oversteitching ends of stand-up collar at the same time. Start and finish the stitch exactly near marked line of stand-up collar connecting seam. Turn ready collar out and press.

3. Sew darts on front parts. Press waist darts towards center of front part, bust darts – upwards. Sew darts on back part. Press darts to center seam. Sew center seam of back part. Serge and press the seam.
4. Fold the placket details right sides together and overstitch outer edge (for right front part it will be outer edge, for left one – inner edge). Cut seam allowances off up to 0.7 cm, slash, turn details out and press. Put decorative stitch along outer edge of the placket at 0.1 cm off the edge. Stitch outer placket to right front part. Slash the seam and press towards placket side. Turn inner placket inside and topstitch into connecting seam. Overstitch left placket the same way.
5. Sew shoulder and side seams. Serge seams and press them to back part.
6. Sew upper stand-up part of collar with the collar into the neckline, turn open edge of lower stand-up collar and topstitch into upper stand-up collar connecting seam. Put decorative stitch along the stand-up collar and collar at 0.1 cm off the edge.
7. Serge separately edges of sleeves. Sew edges up to notch, press seams apart. Sew the sleeve in, easing in on rounded part.
8. Fold cuffs in half and overstitch short sides. Start and finish the stitch exactly near marked line of cuff connecting seam. Turn cuffs out and press. Make pleats on the sleeve according to marked lines. Stitch outer side of cuff to the sleeve. Turn inner side of cuff and topstitch into connecting seam. Serge buttonholes on cuffs and sew buttons.
9. Serge hem of the garment, press onto wrong side and topstitch.
10. Serge buttonholes on right front part, sew buttons on left front part.

#### **TECHNICAL DRAWING:**

