

Sewing Pattern — Bell-Mantle 5718

Recommendations on fabric: crepe-satin for outer mantle, chiffon for inner one.

You will also need: fusing, 2 studs.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams. 2 cm for back/front hems as well as for sleeve hems.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 1 piece
2. Front part – 1 piece
3. Sleeve – 2 pieces
4. Placket – 2 pieces

Chiffon:

1. Back part – 1 piece
2. Front part – 1 piece
3. Sleeve – 2 pieces

Fusing:

1. Placket – 2 pieces

INSTRUCTIONS:

1. Apply the fusing to plackets.
2. Mark placket lines on outer front part. Press plackets along the center right side out. Lay plackets on outer front part right sides together, with their edges to front middle. Stitch them, finish stitching at limiting line. Cut fastening as a slit pocket. Fold seams joining plackets into wrong side, press, then

neaten.

3. Mark placket lines on inner front part. Lay plackets' inner side on inner front part's wrong side, with their edges to front middle. Stitch them, finish stitching at limiting line. Cut fastening as a slit pocket. Fold seams joining plackets into front part's right side, press, then neaten.

4. Lay inner/outer front parts right sides together, fold plackets along the center; overstretch front part's upper corners and front neckline stopping at 3 cm before shoulder edge. Cut allowances in corners, slash roundings. Turn plackets into right side, straighten the fastening. Fix corners at fastening's end along base with double stitching, then neaten. Press ready fastening. Topstitch plackets along joining seam fixing in this way outer side to inner side.

5. Stitch shoulder edge in outer mantle. Press seam allowances apart and neaten them.

6. Stitch sleeves to the garment. Press seams toward sleeves and neaten them.

7. Press the hem into wrong side, fold it under and topstitch.

8. Lay chiffon front/back parts right sides out and stitch shoulder edges. Press seam allowances and neaten them. Stitch sleeves to the garment, laying them right sides out. Press the seam toward the sleeve and neaten it. Lay chiffon mantle's wrong side on outer mantle's right side and overstretch along neckline. Slash rounded allowances, then the garment right side out and press it. Make decorative stitching along the neckline.

9. Sew studs to the fastening.

Our advice: you can take also Velcro for fastening.

TECHNICAL DRAWING:

