

Sewing Pattern — Blouse 5676

Recommendations on fabric: medium/high stretch-knit jersey
(natural or mixed)

You will also need: decorative tape for ties

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: hem – 1.5 cm; all other seams - 1 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Advice:

Knit fabric pieces are sewn together with special stretch-stitch or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

Fabric:

1. Back – cut 1
2. Front – cut 1
3. Front crossover panel – cut 1
4. Back panel (yoke) – cut 4
5. Front panel (yoke) – cut 4

INSTRUCTIONS:

1. Pin back yokes, right sides together, and sew outer edge of armhole.
2. Pin front yokes, right sides together, and sew outer edge of armhole.
3. Open yokes, and with right sides together, sew shoulder seam. Press seam toward back.

4. Serge top edge of the back and front, as well as 3 open edges of front panel. Turn seam allowances onto wrong side, press, and topstitch. Topstitch upper edge of front panel last, having laid the tie under it previously.
5. Make a gathering stitch along edge of armhole on front panel. Gather fullness to fit.
6. Baste in place.
7. Sew outer yoke to armhole of back and front according to marks.
8. Baste front panel to the front along right side seam. Attention: side seam of panel is off the lower edge of front 1.5 cm (hem seam allowance). Sew side seams, inserting the tie into left seam. Serge seams and press toward back.
9. Turn seam allowances of yokes under at neck edge and topstitch edges together. Continuing topstitching along inner edge of armhole.
10. Serge lower edge of garment. Turn onto wrong side, press, and topstitch.

TECHNICAL DRAWING:

