

Sewing Pattern — Top 5631

Recommendations on fabric: natural/mixed fabric

You will also need: natural/mixed fabric

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowances: 1 cm for all seams

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Upper back part – 2 pieces
2. Lower back part – 1 piece
3. Upper front part – 4 pieces
4. Lower front part – 2 pieces
5. Collar – 2 pieces
6. Waistband – 4 pieces

Fusing:

1. Collar – 1 piece

INSTRUCTIONS:

1. Apply the fusing to wrong side of the collar.
2. Stitch upper back dart and press it toward the center.
3. Stitch middle back seam. Neaten the seam and press it.
4. Neaten back armholes, fold them out and topstitch at 0.7 cm.
5. Overstitch the collar. Turn the collar right side out and press it.

6. Lay upper front parts right side together and overstretch armholes. Overstretch wrapping's edge between the waist and the notch. Slash the seam at the notch level. Leave edge segment between the notch and armholes unstitched. Turn upper front part right side out and press it. Process seam allowances. After doing this process this detail as one-layer.
7. Stitch inner collar to upper front/back part. Press the seam toward the collar. Press outer collar's seam allowance inside and topstitch along the seam.
8. Make loose stitches at 0.5 cm from the edge along upper front part's lower edge. Gather the fabric between notches.
9. Stitch front upper/lower parts together. Neaten seams and press them upward.
10. Stitch back upper/lower parts together. Neaten seams and press them upward.
11. Neaten side edges of back/front right side seam. Stitch side edges excluding a slit into right side seam. Neaten left seam and press it forward, press right seam apart pressing closure slit. Make decorative stitch along side slit.
12. Overstretch waistbands. Turn the details right side out and press them.
13. Neaten the hem, fold it under and topstitch at 0.8 cm from the edge.
14. Neaten lower front open edge. Press the edge at 0.8 cm into wrong side. Insert the waistband between pressed allowance and the detail. Topstitch the allowances with the waistband. Fold the waistband out and make fixing stitch.

TECHNICAL DRAWING:

