

Sewing Pattern — Top 5630

Recommendations on fabric: natural/mixed fabric

You will also need: concealed zip; piping

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: 0 cm for back upper edge/armholes/front wrapping, 1 cm for other seams

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Upper back part – 1 piece
2. Lower back part – 1 piece
3. Upper front part – 2 pieces
4. Lower front part – 1 piece
5. Front front part – 1 piece

INSTRUCTIONS:

1. Stitch upper front darts. Slash darts depths and neaten them. Press darts toward the center.
2. Turn in front front part's front open edge. Neaten details' lower edge, fold it under and topstitch at 0.5 cm from the edge. Make pleats as marked. Fix pleat ends with a stitch at 0.5 cm from upper edge.
3. Press the piping along the center and overstitch front neckline (wrapping).
4. Stitch front upper/lower/front parts making a wrapping. Neaten seams and press them upward.
5. Stitch upper/lower back parts together. Neaten seams and press them upward.

6. Stitch side edges excluding closure slit into right side seam. Press right seam frontward, press left seam apart pressing closure slit. Stitch the zipper in.

7. Overstitch armholes/back upper edge with the piping making a strap. Adjust strap's length during a fitting-on. Sew strap's ends to back part. Fold piping's ends neat the zipper under and sew by hand.

8. Neaten the hem, fold it under and topstitch at 0.5 cm from the edge.

TECHNICAL DRAWING:

