

## Sewing Pattern — Dress 5604

Recommendations on fabric: fabric suitable for dresses

You will also need: fusing; 2 tabs; 2 buttons

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowances: 1 cm for all seams, 2 cm for hem allowance

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Front part – 1 piece
2. Back part – 1 piece
3. Front yoke – 1 piece
4. Back yoke – 1 piece
5. Pocket – 2 pieces
6. Strap – 4 pieces
7. Back facing – 1 piece
8. Front facing – 1 piece

Fusing: front/back facings.

### **INSTRUCTIONS:**

1. Apply the fusing to wrong side of front/back facings.
2. Neaten the pocket along the contour and press it according to the pattern. Fold pocket entrance allowance into wrong side and topstitch at 2.5 cm from the edge. Mark pocket place and topstitch the pocket on front part.

3. Stitch side seams. Neaten seams and press them backwards.
4. Make loose stitches along front/back upper parts and make gathering.
5. Lay straps right sides together and overstitch along three edges. Turn straps right side out slashing corners.
6. Stitch back yoke to back part. Neaten back armhole's lower segment. Lay back facing on back part and overstitch along armhole/neckline inserting straps' diagonal edges. Fold back facing into wrong side. Fold back facing's allowance under and topstitch along the seam joining the yoke. Fold armhole allowance into wrong side and topstitch so that the stitch goes along all armhole and back neckline.
7. Stitch front yoke to front part. Neaten front armhole's lower armhole segment. Lay front facing on front part and overstitch along armholes, shoulder edges and neckline. Slash corners. Fold back facing into wrong side. Fold front facing's allowance under and topstitch along the seam joining the yoke. Fold armhole allowances into wrong side and topstitch so that the stitch goes along all armhole and front neckline.
8. Neaten hem allowance. Fold it into wrong side and topstitch.
9. Sew buttons on front yoke and set tabs on straps.

**TECHNICAL DRAWING:**

