

Sewing Pattern — Jacket 5598

Recommendations on fabric: sheer natural/mixed fabric

You will also need: elastic braid; piping of 3 cm width

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 2 pieces
2. Front part – 2 pieces
3. Collar – 1 piece
4. Back facing – 2 pieces
5. Front facing – 2 pieces
6. Sleeve – 2 pieces
7. Cuff – 2 pieces
8. Upper sleeve – 4 pieces

INSTRUCTIONS:

1. Make loose stitch at 0.5 cm from front lower edge. Make gathering at bust line between notches.
2. Press the piping along the center and overstitch middle front edge.
3. Stitch back darts. Press darts toward the center.
4. Stitch middle back seam, neaten it and press.
5. Stitch side/shoulder edges. Neaten seams and press them backwards.

6. Fold the collar right side out and make loose stitches along short edges. Make gathering. Slash corners on front part close to the seam joining the collar. Stitch the collar into the neckline. Cut the seam to 0.5 cm and neaten it. Close the seam with the piping: fold the piping along the center and stitch it to seam (wrong side) so that the piping was at collar's side. Fold the piping to front part closing the seam joining the collar.
7. Stitch side plackets. Stitch outer placket to jacket's lower edge coinciding the notch into front placket and center front edge. Slash the seam close to stitch ends and neaten it. Lay inner/outer plackets right sides together and overstretch placket's open edges; begin and finish stitching close to the seam joining the placket to front part. Turn the placket right side out and press it. Press inner placket's inner edge and topstitch on joining seam.
8. Make gathering along sleeve hem. Stitch upper sleeve to sleeve cap. At other 2 upper sleeves: press the edge of joining to sleeve cap into wrong side. Topstitch upper sleeve on joining seam on wrong side. Press seams. Press the cuff along the center right side out. Turn the cuff and stitch its side edge. Press side seam apart. Press the cuff along the center. Neaten sleeve seam, stitch it and press apart. Stitch cuff's outer side to sleeve hem. Press the seam toward the cuff. Press cuff's open edge. Stitch elastic braid to improve cuff fitting. Topstitch cuff's inner edge along the seam joining the sleeve.
9. Stitch sleeves into armholes according to notches. Neaten joining seams and press them.

TECHNICAL DRAWING:

