

Sewing Pattern — Dress 4231

Recommendations on fabric: thick silk fabric suitable for dresses of two related colors

You will also need: blind zipper, fusing.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, hem of sleeve – 1.2 cm; front part yoke neckline edge - 2 cm; outer seam allowance of the rose – 0 cm; hem of the dress – 3.0 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric 1:

1. Central lower part of the back - 2 details
2. Side lower part of the back - 2 details
3. Central lower part of the front - 1 detail
4. Side lower part of the front - 2 details
5. Rose – 2 details

Main fabric 2:

1. Central upper part of the back - 2 details
2. Side upper part of the back - 2 details
3. Central right part of the front – 1 detail
4. Central upper part of the front – 1 detail
5. Side upper part of the front – 2 details
6. Yoke of the front – 2 details
7. Sleeve - 2 details
8. Back neckline facing – 2 details
9. Front neckline facing – 1 detail
10. Placket – 2 details (is cut on the cross)

Fusing:

1. Back neckline facing – 2 details
2. Front neckline facing – 1 detail

INSTRUCTIONS:

1. Apply fusing to neckline facing.
2. Sew princess edges on upper part of the back, press seam allowances towards center and serge. Sew princess edges on lower part of the back, press seam allowances towards center and serge. Sew upper and lower parts of the back, press seam allowances upwards and serge.
3. Apply fusing to the wrong side of the vent on both details of central lower parts. Mark a central seam line (vent foldline) on the right side. Serge center edge of back part separately on each detail, serging the vent at the same time. Sew center edge of the back from zipper marker up to the edge of the vent. Slash away vent allowance corner on right part. Press seam allowances of the center seam apart, pressing the slit for zipper and the vent. Press right side of the vent at 1 cm onto wrong side and topstitch. Press vent seam allowances to left side and topstitch on the top with machine stitch. Sew the zipper in.
4. Press one longitudinal side on the placket at 1 cm inwards. Stitch non-serged longitudinal edge of the placket to princess edge of central lower part of the front, overlaying the placket onto right side of the detail right side upwards. Seam width is 0.7 cm. The length of the placket is a bit more than princess edges. Cut the surplus away at the end of work.
5. Sew princess edges on upper part of the front, press seam allowances towards center and serge.
6. Stitch upper left part of the front to lower part, press seam allowances upwards and serge. Make and fasten pleats according to markers on central right upper part of the front. Depths are directed upwards. Stitch central right upper part to left one, slashing in the corner, stitching right upper part to lower part at the same time. Press the seam upwards and serge.
7. Serge vertical neckline edge on the yoke of the front and press onto wrong side. Serge lower edge of the front neckline facing. Fold the facing neckline of the front with the front and sew, inserting the front yoke between them. Press seam allowances, turn the facing onto wrong side, fix to the armhole edge.
8. Sew princess edges on lower front part, press seam allowances towards center and serge. Topstitch the pressed edge of the placket onto central part of the front. Stitch upper part of the front to lower one, press seam allowances upwards and serge.
9. Serge inner edge of the back part neckline facing. Fold the dress with facing right sides together, leveling edges of the neckline. Turn the facing, leaving 5 mm to zipper edges and pin to top edge of the dress. Turn seam allowances along zipper on right side of the dress and pin to neckline edge on top of the facing. Overstitch neckline edge, starting and finishing the stitch exactly near shoulder seam marked line. Slash seam allowances on rounded parts, turn details out and press. Tack the facing to zipper tape.
10. Sew shoulder seams, inserting the front between the back and facing of the back. Press seam allowances, serge. Turn the facing onto wrong side.
11. Sew side seams, press seam allowances onto back part and serge.
12. Serge lower edge of sleeve, press onto wrong side and topstitch. Sew edge of sleeve. Press seam allowances and serge. Sew the sleeve into armhole, aligning notches. Press seam allowances and serge.
13. Press seam allowance of the dress hem onto wrong side and undersew with invisible stitches.
14. Fold rose details wrong sides together and level edges. Cut a bias tape from main fabric_2 of 4 cm wide and as long as the outer edge of the rose. Press the bias tape in half lengthwise, unfold and press longitudinal edges to the center marked line. Overstitch outer edge of the rose with bias tape and press. Make the rose into the spiral and tack to the dress, closing connecting seam of right and left upper parts of the front.

TECHNICAL DRAWING:

