

Sewing Pattern — Jacket 5569

Recommendations on fabric: nature/mixed fabric

You will also need: fusing; lining; shoulder pads; 5 buttons; 6 buttons of smaller diameter for sleeve vents.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowances: 1 cm for all seams, 3 cm for garment/sleeve hems

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Side back part – 2 pieces
2. Side front part – 2 pieces
3. Front band – 2 pieces
4. Collar – 2 pieces
5. Center back part – 2 pieces
6. Center front part – 2 pieces
7. Sleeve – 2 pieces
8. Back neckline facing

Lining:

1. Side back part – 2 pieces
2. Side front part – 2 pieces
3. Center back part – 2 pieces
4. Center front part – 2 pieces
5. Sleeve – 2 pieces

Fusing: front band, back neckline facing, center front part, outer collar.

INSTRUCTIONS:

1. Apply the fusing to wrong side of front band, back neckline facing, center front part, outer collar.
2. Stitch back darts and press them towards back center.
3. Lay collars together and overstitch them. Slash seam allowances into corners and turn the collar right side out. Press the collar.
4. Stitch front relieve edges and press them apart.
5. Pin front band on front part right sides together and overstitch along edging. (Overstitching goes upwards at front part side.) Stitch front bands' lower edges to front part along hem line. Cut front edging's rounded upper/lower corners. Topstitch front edgings' overstitching allowances on front bands at 0.2 cm from seams (stop stitching 3 cm before neckline and lower corner). Turn front edgings right side out.
6. Stitch middle back seam and press it apart. Stitch back relieves and press them apart. Stitch shoulder/side seams of the jacket and press them apart.
7. Stitch shoulder edges of back neckline facing and front band, then press them apart. Stitch inner collar into jacket's neckline, stitch outer collar into back neckline facing/front band edges.
8. Press sleeve hems. Stitch sleeve seams and press them apart.
9. Stitch sleeves into armholes according to notches. Stitch shoulder pads.
10. Stitch lining details together, stitch lining sleeves in leaving a hole into a sleeve's seam.
11. Stitch the lining to inner edges of front band/back neckline facing. Press allowances of collar joining seam apart and fix close to seams.
12. Stitch the lining to jacket/sleeve hems. Turn the jacket right side out through the hole in the sleeve. Stitch hole's edge together.
13. Make buttonholes into right front edging, sew buttons on left one. Sew buttons on the vent.

TECHNICAL DRAWING:

