

Sewing Pattern — Jacket 5544

Recommendations on fabric: natural/mixed fabric

You will also need: fusing, lining, shoulder pads, 5 buttons, 6 buttons for sleeve vents

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams, 3 cm for garment/sleeve hems

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Center back part – 2 pieces
2. Side back part – 2 pieces
3. Side front part – 2 pieces
4. Center front part – 2 pieces
5. Front band – 2 pieces
6. Back neckline facing – 1 piece
7. Inner collar – 1 piece
8. Outer collar – 1 piece
9. Upper sleeve – 2 pieces
10. Lower sleeve – 2 pieces

Lining:

1. Center back part – 2 pieces
2. Side back part – 2 pieces
3. Side front part – 2 pieces
4. Center front part – 2 pieces
5. Upper sleeve – 2 pieces
6. Lower sleeve – 2 pieces

Fusing: front band, back neckline facing, center front part, outer collar.

INSTRUCTIONS:

1. Apply the fusing to wrong side of front band, back neckline facing, center front part, outer collar.
2. Stitch back darts and press them towards the center. Stitch front dart and slash its depth. Press front dart apart.
3. Lay outer collar on inner one and overstretch them. Press the collar.
4. Stitch front relieve and press it apart.
5. Pin front band on front part right sides together and overstretch along edging. Stitch lower edges of front bands to front part along marked hem line. Cut seams of lower corners of edging. Topstitch edging's overstretching allowance on front band at closure (stop stitching 3 cm before neckline and lower corner). (Topstitch at 0.2 cm from seam.) Turn edgings right side out.
6. Stitch middle back seam and press it apart. Stitch back relieves and press them apart. Stitch shoulder/side seams and press them apart.
7. Stitch shoulder edges of back neckline facing/front band, then press seams apart. Stitch inner collar into jacket neckline, stitch outer collar into edges of back neckline facing/front band.
8. Stitch elbow seams and vents' corners at upper/slower sleeves. Press elbow seams apart, make notches and press vents. Press sleeve hems into wrong side. Stitch sleeve front seams and press them apart.
9. Stitch sleeves into armholes according to notches. Sew shoulder pads.
10. Stitch lining details together and stitch sleeve in, leaving a hole into right front seam of a sleeve.
11. Stitch the lining to inner edges of front bands/back neckline facing. Press allowances of seam joining the collar apart and fix them close to seams.
12. Stitch the lining to jacket/sleeve hems. Turn the jacket right side out through sleeve hole. Stitch hole's edges together.
13. Make buttonholes into right front part, sew buttons on left one. Sew buttons on vents.

TECHNICAL DRAWING:

