

Sewing Pattern — Jacket 5541

Recommendations on fabric: natural/mixed fabric

You will also need: fusing; 11 eyelets and hooks; lining; shoulder pads

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowances: 1 cm for all seams, 3 cm for garment/sleeve hems

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Side back part – 2 pieces
2. Side front part – 2 pieces
3. Front band – 2 pieces
4. Inner collar – 1 piece
5. Outer collar – 1 piece
6. Upper sleeve – 2 pieces
7. Lower sleeve – 2 pieces
8. Sleeve top – 2 pieces
9. Center back part – 2 pieces
10. Center front part – 2 pieces
11. Back neckline facing – 1 piece

Lining:

1. Side back part – 2 pieces
2. Side front part – 2 pieces
3. Upper sleeve – 2 pieces
4. Lower sleeve – 2 pieces
5. Center back part – 2 pieces
6. Center front part – 2 pieces

Fusing: front band, back neckline facing, outer collar, center front part

INSTRUCTIONS:

1. Apply the fusing to wrong side of front band, back neckline facing, outer collar, center front part, front/back armhole edges.
2. Stitch back darts and press them towards back center. Stitch front darts and slash depths. Press front darts apart.
3. Lay out collar on inner one and overstretch them. Press the collar.
4. Sew eyelets on right front edging, sew hooks on left one. Pin front band on front part right sides together and overstretch along edging. (Overstretch front part upward the notch determining end of stitching the collar in). Stitch lower edges of front bands to front part along marked hem line. Cut seams of upper/lower corners of edging. Topstitch edging's overstretching allowance on front band at closure and at front edging at lapels. (Topstitch at 0.2 cm from seam.) Turn edgings right side out.
5. Stitch front/back relieves and press them apart. Stitch middle back seam and press it apart. Stitch shoulder/side edges and press them apart.
6. Stitch shoulder edges of back neckline facing/front band, then press seams apart. Stitch inner collar into jacket neckline, stitch outer collar into edges of back neckline facing/front band.
7. Make weak stitches at 0.5 cm from sleeves' upper/lower edges, then make gathering.
8. Stitch sleeve tops to upper sleeves. Stitch elbow seams and press them apart. Press sleeve hems into wrong side. Stitch sleeve front seams and press them apart.
9. Stitch sleeve into armholes according to notches. Sew shoulder pads.
10. Stitch lining details together and stitch sleeve in, leaving a hole into right front seam of a sleeve and waistband hole into left side seam.
11. Stitch the lining to inner edges of front bands/back neckline facing. Press allowances of seam joining the collar apart and fix them close to seams.
12. Stitch the lining to jacket/sleeve hems. Turn the jacket right side out through sleeve hole. Stitch hole's edges together.

TECHNICAL DRAWING:

