

Sewing Pattern — Dress with Lay-Down Collar 5522

Recommendations on fabric: natural/mixed fabric.

You will also need: zipper of 25 cm length, lining, piping.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Outer collar – 1 piece
2. Inner collar – 2 pieces
2. Gusset – 6 pieces
3. Middle back part – 2 pieces
4. Side back part – 2 pieces
5. Center front part – 2 pieces
6. Center front part – 2 pieces

Fusing: outer collar.

INSTRUCTIONS:

1. Apply the fusing to wrong side of outer collar.
2. Stitch the gusset to center front part, neaten joining seam 4 cm above the notch. Stitch middle front edge to gusset side edge. Neaten middle edge and gusset side edge. Press middle front seam pressing the gusset.
3. Stitch the gusset to side front part, neaten joining seam 4 cm above the notch. Stitch front relieve seam and gusset side edge. Neaten front relieve seam and press it pressing the gusset.
4. Stitch the gusset to middle back part, neaten joining seam 4 cm above the notch. Stitch middle back edge to gusset side edge. Neaten middle back seam and press it pressing the gusset.
5. Stitch the gusset to side back seam, neaten joining seam 4 cm above the notch. Stitch back relieve

seams and gusset side edge. Neaten relieve seams and press it pressing the gusset.

6. Stitch middle seam of inner collar and press the seam apart. Overstitch inner collar with outer one, turn the collar right side out and press it.

7. Press the piping along the center. Overstitch front/back armholes with piping.

8. Neaten side edges. Stitch side edges and press them apart, leaving closure slit into left seam. Stitch the zipper into slit.

9. Neaten shoulder seams, stitch them together and press them apart.

10. Stitch inner collar into the neckline, fold open edge of outer collar and topstitch it on the seam joining inner collar.

11. Neaten dress hem, fold it under and topstitch at 1 cm from lower edge.

TECHNICAL DRAWING:

