

Sewing Pattern —Short-Sleeved Jacket 5482

Recommendations on fabric: jersey.

You will also need: fusing, separable zipper, decorative cord, braid.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 1 piece
2. Lower front part – 2 pieces
3. Upper front part – 2 pieces
4. Pocket – 2 pieces
5. Pocket facing – 4 pieces
6. Hood – 2 pieces
7. Hood center part – 1 piece
8. Front band – 2 pieces
9. Sleeve – 2 pieces
10. Cuff – 2 pieces
11. Waistband – 1 piece

Fusing: front band, pocket facing.

ADVICE: to prevent seam from stiffing, sew details with special (zig zag) stitch. To prevent hem from stiffing neat it with overlock and then stitch using double needle. Do the same for all edges which must stay elastic.

The above is not for industrial manufacturing.

INSTRUCTIONS:

1. Apply the fusing to wrong side of front band, pocket facing.
2. Sew hood center to hood and neaten the seam. Make eyelets into hood front edge. Neaten hood front edge, fold under and topstitch.
3. Lay facing on pocket and overstretch upper edge. Turn right side out and press facings.
4. Sew pocket facing to pocket. Neaten joining seam.
5. Pin pocket on lower front part.
6. Stitch lower front part to upper front part and neaten the seam. Remove pins.
7. Sew shoulder edges and neaten them laying the braid. Sew side edges and neaten them. Press shoulder/side seams backwards.
Neaten waistband lower edge. Stitch the waistband.
8. Lay front parts right sides together, adjust edges and measure edging lengths. Sew the zipper to edging. Fold edging near zipper and press them down.
9. Neaten front band outer edge. Lay front band on front part right sides together and overstretch along edging (at front part). Overstretch waistband lower corner. Turn edgings right side out and press. Topstitch neaten edge along seam joining waistband.
10. Stitch the hood into neckline. Neaten joining seam. Fix front bands on shoulder seams with 1-cm stitch.
11. Sew sleeve edge. Neaten the seam and press it.
12. Sew cuff side edges. Set the cuffs along the center right side out.
13. Sew cuffs to sleeves lower edges and overstretch cuff upper edges together with sleeves.
14. Sew sleeves into armholes according to notches.
15. Make decorative stitch at 0.5 cm along zipper. Pull the cord into hood eyelets.

TECHNICAL DRAWING:

