

Sewing Pattern — Blouse 4297

Recommendations on fabric: natural/mixed blouse fabric

You will also need: 3 buttons, blind zipper, bias tape.


If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: hem — 1.5 cm, outer edge of frilled front — 0 cm, all other seams -1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

- 1. Back part 2 details
- 2. Front part 1 detail
- 3. Frilled front 1 folded detail
- 4. Collar 1 detail
- 5. Yoke 4 details
- 6. Strap 1 detail

INSTRUCTIONS:

- 1. Sew darts on front part and on back part. Press depths towards center.
- 2. Serge central edges of back part. Sew center edge of back part on section from the notch up to hem. Press apart seam allowance. Put the stitch at 0. 5 cm off the edge of slit.
- 3. Fold the strap right sides together and overstitch on one of the sides. Turn right side out, placing seam in the center of the detail and press. Put the strap onto front part, level edges and tack lower edge of the strap to the neckline.
- 4. Overstitch lower edge of frilled front with bias tape. (Edges of frilled front can also be serged with thin rolled seam). Make pleats on frilled front starting from shoulder seam. Direct tops of pleats towards center. Put the frilled front onto front part and fix along top edge and neckline edge. Topstitch the frilled front onto front part along the marked line. Fold yokes right sides together, inserting front part between them and sew. Fold yokes onto right side and press.



- 5. Sew shoulder seams. Serge seam allowances and press them towards back part.
- 6. Overstitch loop buttonholes. Fold collar in half lengthwise and stitch loop buttonholes from the right side. Overstitch short sides, starting and finishing the stitch exactly near marked line. Sew outer side of collar into the neckline. Round the collar with the strap and tack to the allowance of inner side of collar. Turn inside seam allowance of inner side of collar and topstitch into outer side connecting seam.
- 7. Cut bias tape of 4 cm wide and as long as the armhole + 4 cm. Fold the bias tape in half lengthwise and press. Put the bias tape onto armhole and stitch. Slash seam allowances. Fold the bias tape onto wrong side and topstitch.
- 8. Sew right side edge. Serge seam allowance and press it towards back part. Serge edges of left side seam. Sew left side seam, leaving a section for zipper. Press apart the seam. Sew in zipper.
- 9. Serge hem of garment. Fold seam allowance onto wrong side, press and topstitch.
- 10. Sew buttons on collar.

TECHNICAL DRAWING:

