

Sewing Pattern — Jacket 5328

Recommendations on fabric: VELOUR

You will also need: fusing, 6 buttons

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance : on hem – 2 cm, all other seams - 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Collar – 2 pieces
2. Collar stand – 2 pieces
3. Back – 1 piece
4. Front – 2 pieces
5. Sleeve – 2 pieces
6. Cuff – 2 pieces
7. Front facing – 2 pieces

OUR ADVICE: You can make decorative stitch, look like handmade stitch on the cuffs, slit edges and hem.

Fusing: front facings, under collar, collar stand pieces, under cuffs.

INSTRUCTIONS:

1. Apply fusing to the wrong side of the front facings, under collar, collar stand pieces, and under cuffs.
2. Make up and shape the collar.
3. Stitch the collar stands inserting the main collar between them.
4. Stitch front/back darts. Press them.

5. Neaten the front facing raw edges. With right sides together, overstretch the front centre/lower edges with the front facing up to the notches showing the collar position. Trim the seam allowances on the corners. Understitch the seam allowances as following: at the collar segment – on the front facing, at the lapel segments – on the front piece.
6. Neaten side/shoulder edges and hem. Stitch the side seams up to the notches and press them open. Press the slits. Stitch the shoulders seams and press them open.
7. Stitch the collar stand to the neckline. Stitch the front facing to the lower edge of the collar stand.
8. Neaten the sleeve side edges. Stitch them up to the notches. Press the seams open. Press the slits slightly and topstitch very close to the fold lines.
9. Fold the top edge of the cuffs to the wrong side. Stitch the side seams. Trim the seam allowances on the corners diagonally. Turn the cuffs right side out. Press them. Stitch the lower cuff edges to the lower edges of the sleeves. Topstitch the upper cuffs to the sleeves through the under cuff top edges.
10. Stitch the sleeves to the armholes according to the notches. Neaten the seams.
11. Fold the hem to the wrong side and sew it by a hand stitch.
12. Make buttonholes in the right front piece and in the cuffs. Attach the buttons according to the marks.

TECHNICAL DRAWING:

