

Sewing Pattern — Coat 5319

Recommendations on fabric: wool or semi-wool

You will also need: fusing; 1 button; lining

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance : 1 cm for all seams

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Upper center back part – 2 details
2. Lower center back part – 2 details
3. Upper side back part – 2 details
4. Lower side back part – 2 details
5. Inner collar – 1 detail
6. Outer collar – 1 detail
7. Upper side front part – 2 details
8. Lower side front part – 2 details
9. Upper center front part – 2 details
10. Lower center front part – 2 details
11. Front band – 2 details
12. Flap – 4 details
13. Sleeve – 2 details

Lining:

1. Center back part – 1 detail
2. Side back part - 2 details
3. Side front part – 2 details
4. Center front part – 2 details
5. Bag – 4 details
6. Sleeve – 2 details

Fusing: front band, inner collar, upper center front part, upper side front part armhole, upper center back part, upper side back part armhole, pocket strengthener; hem allowances: lower center front part, sleeve, lower side back part, lower center back part.

INSTRUCTIONS:

1. Strengthen the front band, inner collar, upper center front part, upper side front part armhole, upper center back part, upper side back part armhole, pocket strengthener; hem allowances: lower center front part, sleeve, lower side back part, lower center back part with clue interfacing
2. Overstitch inner collar with outer one (right sides together). Cut, then turn the collar right side out.
3. Fold the flap and under-flap right sides together, then trim the corners and overstitch. Cut pocket corners seam allowances, then turn right side out. Overtack the flap, then press it on under-flap side, creating the edging of 0.2-0.1 cm on the flap side.
4. Sew upper center front part to lower center front part. Sew upper side front part to lower side front part. Press seams downward and make decorative stitch on 0.5 cm from joining seam.
5. Sew front relieves and press them into front part center. Make decorative stitch on 0.5 cm from joining seam.
6. Tack or fix pocket entrance with the pocket strengthener. Fold pocket facing wrong side inside, then press. Mark auxiliary line on pocket facing, along facing folding, for topstitching the facing. Mark auxiliary line on the flap (for flap topstitching) along flap upper edge, measuring flap width along all the length. Mark auxiliary line parallel to pocket entrance, for sewing the flap and pocket facing. Sew the bag to the flap. Sew flap with the Hessian) to lower side front side. Sew the facing lower center front part. Finish stitch ends near parallel marking of pockets. Check facing and the flap topstitching on the wrong side (stitched should be parallel). Cut pocket entrance. Make diagonal cuts on 1-1.5 cm from pocket end. Through these holes, turn into wrong side the facing and flap joining seam, trim edges. Fit facing end so that facing pressed folding was accurately to flap joining seam. Fix pocket ends on the wrong side with double inverse stitch on corner bases. Sew the bag.
7. Pin the front band and front part right sides together, then overstitch along the marked line. Overstitch on the front part upwards the notch defining the end of collar sewing into. Sew front bands lower edges to front part strictly along marked hemline. Cut upper and lower seams corners. Make decorative stitch on 0.5 cm from the edge overstitching seam.
8. Sew upper side back part to lower side back part. Sew upper center back part to lower center back part. Press the seams under, then make decorative stitch along joining seam on 0.5 cm from the edge.
9. Sew back relieves, press toward the back part center, then make decorative stitch along joining seam on 0.5 cm from the edge.
10. Sew shoulder and side seams, then press apart.
11. Sew inner collar to the neckline, then sew outer collar to front bands.

12. Sew the sleeves into the armholes according to notches. Sew shoulder pads and sleeve heads.
13. Sew lining to inner edges of front bands and outer collar. Press collar joining seams allowance apart, then fix near seams. Sew the lining to fabric coat hem. Turn the coat right side out through the hole in the sleeve, then sew the hole.
14. Work buttonholes into right front part, then sew buttons to left one.

TECHNICAL DRAWING:

