

Blouse With Shaped Hem - Sewing Pattern #2033

Recommendations on fabric: thick natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 10 buttons; 8 push buttons.

Seam allowances: all seam allowances – 1.0 cm

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back yoke - cut 1
2. Back - cut 1 on fold
3. Front - cut 2
4. Front facing - cut 2
5. Back facing - cut 2
6. Collar - cut 2
7. Stand collar - cut 2

- 8. Sleeve - cut 2
- 9. Cuff - cut 2

Fusible interfacing:

- 1. Collar - cut 1
- 2. Stand collar - cut 1
- 3. Cuff - cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew back yoke to yoke. Serge seams and press towards top. Pin back facing onto back, right sides together. Sew side edge. Fold facing onto wrong side, turn under the outer seam allowance and topstitch along the marked line. Serge hem of sleeve. Fold inside the seam allowance and topstitch.
3. Pin front facing onto front right sides together. Sew side edge. Fold facing onto wrong side, turn under the outer seam allowance and topstitch along the marked line. Turn under the outer edge of one-piece placket and press. Fold one-piece placket onto right side and sew the lower corner. Trim corner, fold the placket onto wrong side. Turn under the seam allowance of placket and topstitch along the marked line from the right side.
4. Pin side edge of front onto side edge of back, matching plackets and baste pieces together along the armhole edge.
5. Sew shoulder seams, press towards the back and serge.
6. Pin upper collar to lower collar, right sides together. Sew ends of collar and collar fall. Trim seam allowances. Turn the collar right side out, straighten and press. Pin stand collars together, right sides together, put ready collar between them, adjust notches and sew, sewing ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press.
7. Sew outer stand collar with collar into neckline, fold inside open edge of internal stand collar and stitch in the ditch. Sew a decorative stitch along collar and stand collar at 0.1 cm.
8. Serge sleeve edges separately. Sew sleeve seam from notch upwards, press the seam apart. Sew a fastening stitch along the slit at 0.1 cm from the edge. Sew sleeves into armholes. Serge the seam allowances and press to sleeve.
9. Fold cuff in half lengthwise, right sides together and sew side seams. Turn the piece right side out, press. Sew the outer part of the cuff to the sleeve, fold inside the inner side of the cuff, and topstitch into the seam of the outer cuff cuffs.

10. Make buttonholes and sew on buttons on front, stand collar and cuffs. Sew on buttons according to button holes. Install push buttons on side edges of front and back.

TECHNICAL DRAWING:

