

Jacket With Buckle - Выкройка #2068

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; lining; shoulder pads; 1 buckle.

Seam allowances: all seams 1 cm. Seam allowance for hem of sleeve - 3.0 cm.

Attention! Pattern pieces are drafted as seen from the right side, when cutting, please place them with the text and markings down onto the fabric.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:

1. Upper center back - cut 2
2. Lower center back - cut 1
3. Upper side back - cut 2
4. Lower side back - cut 2
5. Upper center front - cut 2

6. Upper side front - cut 2
7. Lower side front right - cut 1
8. Lower center front right - cut 1
9. Lower front left - cut 1
10. Lower collar - cut 1
11. Upper collar - cut 1
12. Center front facing - cut 2
13. Back neck facing - cut 1
14. Upper sleeve - cut 2
15. Lower sleeve - cut 2
16. Strap - cut 2

Lining:

1. Upper center back - cut 2
2. Lower center back - cut 1
3. Upper side back - cut 2
4. Lower side back - cut 2
5. Upper center front - cut 2
6. Upper side front - cut 2
7. Lower side front right - cut 1
8. Lower center front right - cut 1
9. Lower front left - cut 1
10. Upper sleeve - cut 2
11. Lower sleeve - cut 2

Attention! Front and back from lining are cut using the pattern blocks for self fabric, with the exception for the areas of center front facing and back neckline facing.

Fusible interfacing:

1. Upper center front - cut 2
2. Center front facing - cut 2
3. Back neck facing - cut 1
4. Upper collar - cut 1

Инструкции:

1. Apply fusible interfacing. Apply fusing on front along the lapel fold , its width should equal 1 cm (fusible interfacing).
2. Fold strap in half lengthwise right sides together and sew along long side and one short side. Trim away corners, turn the piece right side out, press.
3. Sew center seam on upper back, press the seam apart. Sew upper center back to upper side back, press

seam apart. Sew upper center front to upper side front, press seam apart.

4. Sew and press apart the shoulder and side seams of upper part, inserting the strap into the left side seam.

5. Sew center lower back to side lower back, press seam apart. Sew right lower center front to right lower side front, press seam apart. Sew side edges of lower parts and press apart.

6. Repeat for lining of lower part. Pin Shell to lining and sew lower edge. Clip into curves, turn right side out, press. Make and baste a box pleat on lower left front.

Sew lower part of Shell to upper part of Shell (seam allowances along center front protrude by 1 cm).

7. Pin upper collar to lower collar and sew the corners and the outer edge. Start and stop sewing exactly at the marked line of the seam between collar and garment. Trim away corners, snip into seam allowance near the mark. Turn the collar right side out, straighten and press.

8. Sew and press apart the shoulder edges of the back neckline facing and of the center front facing.

9. Place center front facing onto front right sides together, pin together and sew along the center front edge, inserting strap. Sew upwards up to the notch marking the end of collar seam. Trim away corners. Topstitch seam allowance along center front edge onto center front facing along the closure, and onto front along the part, which is folded away. Place stitch line at 0,2 cm from seam. Turn center front facings right side out, straighten seams.

10. Sew lower collar into neckline of Shell, sew upper collar into back neckline facing and center front facing. Press seam allowances of the collar seam apart and slipstitch them together close to the seam.

11. Sew elbow seam on sleeve, press the seam apart. Press the hem of sleeve. Sew and press apart front sleeve seam. Sew sleeves into armholes matching notches, adjusting ease along upper side of sleeve cap. Sew shoulder pads.

12. Sew seams and sew in sleeves on upper pattern pieces from lining, leaving an opening for turning in front right sleeve seam.

13. Sew lining to inner edges of the central front facings and to back neckline facing. Turn center front facing and lining onto wrong side, and sew them to jacket, placing the lower part between Shell and lining. Turn jacket right side out through the opening in seam. Sew lining to hem of sleeve. Sew the opening in the sleeve closed.

14. Thread strap into buckle and slipstitch.

Технический рисунок:

