

Blouse With Pleats And Chiffon Overlay - Выкройка #2092

Recommendations on fabric: natural/mixed fabrics suitable for blouses; companion fabric - chiffon.

You will also need: fusible interfacing; 4 buttons.

Seam allowances: Seam allowance for hem of garment and hem of sleeve - 1.5 cm; other seams - 1 cm.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Inner back - cut 1 on fold
2. Inner front - cut 1 on fold
3. Front inset - cut 2
4. Back yoke - cut 1 on fold
5. Placket - cut 4
6. Sleeve - cut 2
7. Sleeve decorative tab - cut 2

Chiffon:

1. Outer back - cut 1 on fold
2. Outer front - cut 1 on fold

Fusible interfacing:

1. Placket - cut 2

Инструкции:

1. Apply fusible interfacing.
2. Make pleats on outer back, fold bulk towards center. Pin outer back onto inner back, wrong side onto right side and baste together along upper edge. Sew back yoke to back, press seam allowances towards yoke and serge.
3. Pin plackets together by two and sew the outer edge. Turn pieces right side out straighten and press. Make buttonholes on right placket. Sew plackets to front inset, press seam allowances towards inset and serge. Pin right inset onto left inset and baste together along lower edge.
4. Make pleats on outer front, fold bulk towards center. Pin outer front onto inner front, wrong side onto right side and baste together along upper edge. Sew inset to front, press towards front and serge.
5. Sew shoulder seams, press towards the back and serge. Sew side edges on inner and outer pieces separately, press towards the back and serge. Baste together along the armhole edge, treat as one piece in the future.
6. Cut (or take ready) a bias tape, its length should equal the length of the neckline + 4 cm. Fold bias tape in half lengthwise right side out and press. Unfold the piece, press edges towards the fold. Sew bias tape to neckline (pin bias tape to neckline edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line).
7. Fold decorative tabs in half lengthwise right sides together and sew along longer and one shorter edge. Turn right side out, snipping the seam allowances in corners, straighten and press. Serge the unfinished shorter edge. Topstitch decorative tabs according to the markings onto the wrong side of sleeves.
8. Sew sleeve seams, press towards back and serge. Sew sleeves into armholes, serge and press.
9. Serge hem of garment and hem of sleeve, turn inside and topstitch.
10. Sew on the buttons on the left placket. Make buttonholes on decorative tabs, sew on buttons onto sleeves.

Технический рисунок:

