

Tunic With Tucks - Sewing Pattern #2112

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing, 11 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem of garment and hem of sleeve - 2.0 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 2
3. Sleeve - cut 2
4. Sleeve decorative tab - cut 2
5. Stand collar - cut 2

Fusible interfacing:

1. Stand collar - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to outer stand collar and to one-piece plackets on the front.
2. Make tucks on front and topstitch them from shoulder seam up to notch (bulk should be on the right side, and directed away from center).
3. Serge the edge of one-piece placket on the front. Fold placket onto wrong side, press and topstitch along the marked line.
4. Sew shoulder and side seams, press towards the back and serge.
5. Pin stand collars together right sides together sew outer edges. Start and stop sewing exactly at the marked line of seam. Clip into curves. Turn the finished stand collar right side out and press.
6. Sew outer stand collar into neckline, press seam allowances at stand collar. Turn under the unfinished edge of inner stand collar and stitch in the ditch.
7. Fold decorative tabs in half lengthwise right sides together and sew along longer and one shorter edge. Turn right side out, snipping the seam allowances in corners, straighten and press. Serge the unfinished shorter edge. Topstitch decorative tabs according to the markings onto the wrong side of sleeves.
8. Sew sleeve seams, press towards back and serge. Sew sleeves into armholes, serge and press.
9. Turn under the hem, and hem of sleeve, two times by 1 cm and topstitch.
10. Make buttonholes on right placket and on stand collar, sew on buttons on the left one. Make buttonholes on decorative tabs. Sew on buttons on sleeves.

TECHNICAL DRAWING:

