Dress With Decorative Piping - Выкройка #2141



Recommendations on fabric: natural/mixed fabrics with elastane suitable for dresses.

You will also need: dress zipper; decorative piping (the approximate length is mentioned on the pattern block for Front).

Seam allowances: all seams 1 cm. Seam allowance for hem of garment - 3 cm.

Attention! Pattern blocks have markings and texts from the right side. Take this into account when cutting the fabric-some of the pattern blocks need to be laid onto fabric with their wrong side on top.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back – cut 2
2. Right front – cut 1
3. Center front – cut 1

4. Left front – cut 1
5. Sleeve — cut 2
6. Back neck facing – cut 2

Инструкции:

1. Sew darts on front, press bulk towards top.

2.Pin decorative piping onto Right Front and sew. Serge and press towards the main piece. Topstitch seam allowance onto the main piece.

3. Pin decorative piping onto Center Front and baste together. Sew Right Front to Center Front. Serge the seam allowance and topstitch it onto the center part. Sew the left front in the same way.

4. Sew darts on back. Press bulk towards center. Serge the center back edges separately. Sew center edge from notch for zipper to bottom. Press the seam apart. Sew in zipper.

5. Serge the outer edges of the Back Facing. Pin Facing onto Back, right sides together, and sew the back neckline. Sew shoulder seams, inserting the Front between the Back and the Facing.

6. Sew side seams. Serge seams and press towards back.
7. Sew a gathering stitch along a sleeve cap and gather fullness or make pleats as desired. Sew in the sleeves.

8. Pin decorative piping at the lower edge of sleeve and sew. Serge the seam allowances and press onto sleeve. Topstitch seam allowance onto the main piece.

9. Serge the lower edge of garment. Press seam allowance on lower edge onto wrong side and topstitch.

Технический рисунок:

