

Blouse With Fly Yokes - Sewing Pattern #2181

Recommendations on fabric: natural/mixed fabrics suitable for blouses, silk.

Seam allowances: Seam allowances - 1 cm. Seam allowance for hem of garment - 2 cm. Seam allowance on lower edge of sleeve - 0 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 1 on fold
3. Sleeve - cut 2
4. Front lining - cut 1 on fold
5. Back lining- cut 1 on fold
6. Fly yoke 1 - cut 2

7. Fly yoke 2 - cut 2

INSTRUCTIONS:

1. Sew front darts, press bulk towards top.
2. Fold fly yoke 1 in half wrong sides together and pin onto front. Fold fly yoke 2 in half wrong sides together and pin at yoke 1. Attach yokes to front, treat as one piece in the future.
3. Sew shoulder and side seams, press seams towards back and serge.
4. Sew shoulder and side seams of lining. Serge seams and press towards back. Serge lower edge. Pin together lining to main fabric right sides together and sew the neckline. Clip seam allowances, fold lining towards wrong side and press. Baste together lining to the main piece along the armhole edge.
5. Sew sleeve seam, press seams towards back and serge. Finish the lower edge of sleeve with thin rolled hem. Sew sleeves into armholes matching notches and adjusting ease, serge and press.
6. Seam allowance along hem press towards 1 cm, then again at 1 cm and topstitch.

TECHNICAL DRAWING:

