

Light Coat - Sewing Pattern #2289

Recommendations on fabric: natural/mixed thin fabric suitable for coats, or natural/mixed suiting fabric.

You will also need: fusible interfacing; lining; 6 buttons.

Seam allowances: all seams 1 cm. Upper pocket edge - 3 cm, seam allowance for hem 3 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Front - cut 2
2. Back - cut 1 on fold
3. Yoke - cut 2
4. Collar - cut 2
5. Stand collar - cut 2
6. Center front facing - cut 2
7. Back neck facing - cut 1

- 8. Sleeve – cut 2
- 9. Pocket – cut 2
- 10. Flap – cut 4
- 11. Cuff – cut 2

Lining:

- 1. Front – cut 2
- 2. Back - cut 1 on fold
- 3. Sleeve – cut 2
- 4. Yoke – cut 2

Fusible interfacing:

- 1. Center front facing – cut 2
- 2. Back neck facing – cut 1
- 3. Collar - cut 1
- 4. Cuff – cut 2
- 5. Flap – cut 2
- 6. Stand collar – cut 2

Attention: The back, fronts and sleeves from lining are cut using the pattern blocks for the main fabrics except for the width of the back facing and center front facing correspondingly.

INSTRUCTIONS:

- 1. Apply fusible interfacing.
- 2. Serge the upper edge of pocket, fold inside the seam allowance and topstitch. Fold under the side and lower seam allowances of pocket, and press. Pin pocket onto front according to markings and topstitch along side and lower edges.
- 3. Pin flaps together pairwise right sides together and sew along the side edges and the lower edge. Turn right side out flap onto right side and press. Sew a decorative stitch around all edges at 0.5 cm from the edge. Pin flap onto front and baste together with the seam allowance on main fabric.
- 4. Sew front yoke to front. Press seam allowance towards top. Sew a decorative stitch at 0.5 cm from seam.
- 5. Sew shoulder edges of coat and press apart. Sew in sleeves. Press the seam apart.
- 6. Sew side seam, and continue sewing the sleeve seam. Press seam allowance towards back.
- 7. Sew cuff seam, press the seam apart. Fold cuff in half lengthwise and press. Sew cuff to lower edge of sleeve.

8. Pin collars together, right sides together, and sew collar ends and collar fall. Trim away corners, turn right side out and press. Sew a decorative stitch along the collar fall and corners at 0.5 cm from the edge. Pin together stand collars right sides together and sew, inserting collar. Start and stop stitching exactly at the marked seam of stand collar into neckline.
9. Sew and press apart the shoulder edges of the back neckline facing and of the center front facing.
10. Place center front facing onto front right sides together, pin together and sew along the center front edge. Trim away corners.
11. Sew lower stand collar into the coat neckline, sew upper stand collar into the neckline of back facing and center front facing. Press apart the seam allowances of stand collar and slipstitch together close to the seam.
12. Sew seams on lining, leaving an opening in left sleeve.
13. Sew lining to inner edges of center front facings, back neckline facing and lower edge of coat. Sew lining to hem of sleeve.
14. Turn the coat right side out through the opening in sleeve. Sew the opening in sleeve lining closed.
15. Sew a decorative stitch along the center front edge along the marked line. Make buttonholes on the left front and left stand collar. Sew on buttons onto the right stand collar and onto right front.

TECHNICAL DRAWING:

