

## Jacket With Shawl Collar - Sewing Pattern #2296

Recommendations on fabric: soft natural/mixed suiting fabrics. Knit fabric of small stretchiness.

You will also need: fusible interfacing.

Seam allowances: all seams 1 cm. Seam allowance along hem of jacket and hem of sleeve - 3 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 2
3. Sleeve - cut 2
4. Center front facing - cut 2
5. Back neck facing - cut 1

Fusible interfacing:

1. Center front facing - cut 2
2. Back neck facing - cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing.
2. Sew darts on front, press bulk towards top.
3. Sew collar seam, after having pinned fronts right sides together, press seam apart. Sew and press apart shoulder seams of jacket, serge. Clip into seam allowance of shoulder seam on front and sew collar into back neckline, press seam allowances towards collar.
4. Sew, clip into corner and press apart shoulder seams of back neckline facing and buttonstand. Sew collar edge, press seam apart. Sew collar into neckline facings, press seam apart. Serge the outer edge of center front facings and of neckline facing.
5. Pin facings and center front facings to front right sides together and sew buttonstand, neckline and lower corner. Trim away corners, clip into curves. Fold center front facings (buttonstands) onto right side, straighten seams, press. Slip stitch together seam allowances along collar seams.
6. Sew side seams, press seams towards back and serge.
7. Sew sleeve seam, press towards back and serge. Sew sleeves into armholes matching notches, serge and press.
8. Serge hem of garment and hem of sleeve, press onto wrong side and topstitch. Sew a decorative stitch along center front edge and collar at 0.5 cm from edge.

## **TECHNICAL DRAWING:**

