

Blouse With Stand Collar - Sewing Pattern #2302

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 9 buttons.

Seam allowances: all seams 1 cm. Seam allowance along upper edge of pocket – 2 cm. Seam allowance for hem of garment – 2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Cuff – cut 2
4. Stand collar – cut 2
5. Pocket – cut 1

Fusible interfacing:

1. Cuff – cut 2
2. Stand collar – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Serge upper seam allowance of pocket, press onto wrong side and topstitch. Press side and lower seam allowances of pocket onto wrong side. Pin pocket onto front according to markings and topstitch.
3. Sew shoulder seams, press towards the back and serge. Sew side seams up to notch on sleeve, press the seam apart and serge. Sew a fastening stitch along the slit at 0.1 cm from the edge.
4. Pin stand collars together right sides together and sew outer edges (start and stop stitching exactly at the marked line of the connecting seam). Clip into curves, trim away corners. Turn stand collar right side out and press.
5. Fold the one-piece placket onto wrong side and press along the marked line. Turn under the seam allowance of the inner edge and topstitch onto front along the fold. Sew outer stand collar into neckline, fold inside open edge of internal stand collar and stitch in the ditch.
6. Fold cuff in half lengthwise, right sides together and sew side seams. Turn the piece right side out, press. Make and baste two pleats along the lower edge of the sleeve. Sew the outer part of the cuff to the sleeve, fold inside the inner side of the cuff, and topstitch into the seam of the outer cuff cuffs.
7. Make buttonholes on right front, sew on buttons on left front. Make buttonholes and sew on buttons onto cuffs and onto stand collar.

TECHNICAL DRAWING:

