Blouse With Yoke - Выкройка #2374

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 9 buttons.

Seam allowances: Seam allowance for hem of garment – 2.5 cm; other seams – 1 cm.



О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back yoke - cut 1 on fold
2. Back - cut 1 on fold
3. Front yoke - cut 2
4. Front - cut 2
5. Placket — cut 4
6. Sleeve – cut 2
7. Cuff – cut 2

8. Back neck facing – cut 1
9. Front neck facing – cut 2

Fusible interfacing:
1. Placket — cut 2
2. Cuff – cut 2
3. Back neck facing – cut 1
4. Front neck facing – cut 2

Инструкции:

1. Apply fusible interfacing.

2. Sew a gathering stitch along the upper edge of the back and gather fullness. Sew yoke to back, press towards top and serge.

3. Sew outer placket to front, press seam allowances at placket. Pin inner placket to front right sides together and sew the neckline and center front facings. Trim away corners, turn the piece right side out, straighten, press. Fold under the inner edge of the inner placket and stitch in the ditch into the connecting seam of outer placket.

4. Sew a gathering stitch along upper edge of front and gather fullness. Sew yoke to front (the lower edge of yoke at the neckline is longer than the upper edge of front by 1 cm), press towards top and serge.

5. Sew side and shoulder seams, press towards the back and serge.

6. Sew the shoulder seams of the neckline facings, press the seam apart. Serge the outer edge. Pin facing to garment right sides together and sew the front neckline and the back neckline. Clip into curves, turn facing onto wrong side, straighten, press. Slipstitch to garment along shoulder seams and yoke seams.

7. Serge the sleeve edges separately. Sew sleeve seam from armhole up to mark for slit, press the seam apart. Topstitch slit at 0.1 cm from fold. Sew sleeves into armholes, serge and press. Sew a gathering stitch along lower edge of sleeve and gather fullness.

8. Fold cuff in half lengthwise, right sides together and sew side seams. Turn the piece right side out, press. Sew outer side of cuff to sleeve, fold the seam allowance of the inner cuff inward and stitch in the seam attaching the outer cuff.

9. Turn hem under inside at 1 cm, then at 1.5 cm and topstitch.

10. Make buttonholes on right placket, sew on buttons on the left one. Make buttonholes and sew on buttons onto cuffs.

Технический рисунок:

