Blouse With Embroidery - Выкройка #2532

Recommendations on fabric: natural/mixed fabrics suitable for blouses. For Example, embroidered cotton.



You will also need: fusible interfacing.

Seam allowances: all seams 1 cm. Seam allowance along the center edge of the front – 0 cm. Seam allowance along the lower edge of the garment – 1.5 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back - cut 1 on fold
2. Yoke – cut 1
3. Front – cut 2
4. Sleeve – cut 2
5. Stand collar — cut 2
6. Cuff – cut 2

Fusible interfacing:
1. Stand collar – cut 1
2. Cuff – cut 2

Инструкции:

1. Apply fusible interfacing.

2. Sew a row of gathering stitches along the upper edge of the back between the marks with reduced upper thread tension and gather fullness. Sew yoke to back, press towards top and serge.

3. Sew darts on front, press bulk towards top.

4. Cut a bias tape from self fabric (or take ready), its width should equal 4 cm and its length should equal the length of the center front edge + 4 cm. Sew the bias tape to the center front edge (sew to the edge, fold onto wrong side, fold inside the open edge and topstitch into the seam). Put right front onto left front, matching center lines, and topstitch into the seam of the bias tape.

5. Sew side and shoulder seams, press towards the back and serge.

6. Pin stand collars together right sides together and sew outer edges. Start and stop sewing exactly at the marked line of seam. Clip into curves, turn stand collar right side out and press.

7. Sew outer stand collar into neckline, press seam allowances at stand collar. Turn under the unfinished edge of inner stand collar and stitch in the ditch.

8. Sew sleeve seam, press towards the back and serge. Sew a gathering stitch along the lower edge of garment and gather fullness. Sew sleeves into armholes, serge and press.

9. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise and press right side out. Sew the outer side of cuff to the sleeve, press the seam allowances towards cuff. Fold inside the open edge of the inner side of the cuff and topstitch into seam of.

10. Serge the seam allowance along the hem of garment, press onto wrong side and topstitch.

Технический рисунок:

