

## Dress With Yoke - Выкройка #2589

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing, dress zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of garment - 2.0 cm.

### О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

### О требуемой длине ткани:

**Внимание!** В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



## РАСКРОЙ:

### Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Side front - cut 2
4. Center front - cut 1 on fold
5. Yoke - cut 4
6. Back neck facing — cut 2
7. Front neck facing - cut 1

Fusible interfacing:

1. Front neck facing — cut 1
2. Back neck facing - cut 2

### **Инструкции:**

1. Apply fusible interfacing.
2. Serge center back edges separately. Sew the center back seam from zipper mark to hem. Press the seam apart.
3. Sew side backs to center back. Serge seams and press towards center.
4. Sew side fronts to front. Serge seams and press towards center.
5. Serge the outer edge of neckline facing. Pin facing onto front, right sides together and sew the neckline opening and corners. Clip seam allowances, trim away corners, fold facing onto wrong side and press.
6. Pin yokes together pairwise right sides together, insert the front in between and sew along lower edge, at the same time sewing neckline edge. Fold away yokes onto right side, straighten seams and press.
7. Serge outer edge of back neckline facing. Pin neckline facing onto Back and sew neckline exactly up to the marked line of shoulder seam. Clip seam allowances, fold facing onto wrong side and press.
8. Sew shoulder seams, inserting the Front between the Back and the Facing, press towards the back and serge. Sew side seams, press seam allowances towards back, serge.
9. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape onto armhole edge from the right side and sew, fold the bias tape onto wrong side and topstitch onto main piece along the fold.
10. Sew side seams. Serge seams and press towards back.
11. Serge the lower edge of garment, press onto wrong side and topstitch.

### **Технический рисунок:**

