Office Blouse - Выкройка #2666



Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 9 buttons.

Seam allowances: Seam allowance for hem of garment – 2 cm; other seams – 1 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back - cut 1 on fold
2. Front - cut 2
3. Sleeve – cut 2
4. Collar — cut 2
5. Stand collar – cut 2
6. Cuff – cut 2

Fusible interfacing:
1. Collar — cut 1
2. Stand collar – cut 1
3. Cuff – cut 2

Инструкции:

1. Apply fusible interfacing. Apply fusible interfacing to the one-piece placket.

2. Make and baste pleats along the upper edge of the front piece. The inner part of the pleats is directed towards center.

3. Fold the one-piece placket onto wrong side and press according to marked line center front facings. Fold inside the longer seam allowance of the one-piece placket and topstitch placket onto front.

4. Sew shoulder and side seams, press towards the back and serge.

5. Pin upper collar to lower collar, right sides together, sew ends of collar and collar fall. Trim seam allowances, turn the collar right side out, straighten and press. Sew a decorative stitch at 0.5 cm from the edge. Pin stand collars together, right sides together, put ready collar between them, adjust notches and sew, sewing ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press. Sew upper stand collar with collar into neckline, fold raw edge of lower stand collar and stitch-in-the-ditch along seam of upper stand collar.

6. Cut slit on sleeve along the marked line. Cut bias tape from main fabric (or take ready), its width should equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew bias tape to slit of sleeve (pin bias tape to slit edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line). Make and baste the pleat on sleeve. The bulk is directed away from the closure.

7. Sew sleeve seam, press towards the back and serge. Sew a gathering stitch along a sleeve cap and gather fullness. Sew sleeves into armholes, serge and press.

8. Fold cuffs in half lengthwise right sides together and sew side edges. Start and stop stitching exactly at the marked line of the cuff seam. Turn the piece right side out, press. Sew outer side of cuff to sleeve, fold the seam allowance of the inner cuff inward and stitch in the seam attaching the outer cuff.

9. Turn hem under inside at 1 cm, then again at 1 cm and topstitch.

10. Make buttonholes on right front, sew on buttons on the left one. Make buttonholes and sew on buttons onto cuffs.

Tip. For decoration, you can make button holes on the collar ends, and sew on buttons on the front accrodingly.

Технический рисунок:

