Blouse With Shoulder Pleats - Выкройка #2715

Recommendations on fabric: natural/mixed fabrics suitable for blouses with elastane.



You will also need: fusible interfacing; 4 buttons.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment – 2 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:

1. Back – cut 2
2. Front – cut 2
3. Sleeve – cut 2
4. Cuff – cut 2
5. Front neck facing – cut 2
6. Back neck facing – cut 1

Fusible interfacing:

1. Cuff – cut 2
2. Front neck facing – cut 2
3. Back neck facing – cut 1

Инструкции:

1. Apply fusible interfacing.

2. Sew darts on back. Press bulk towards center. Sew center back seam. Serge seam and press towards left.

3. Make and baste pleats on the shoulder edges of the front pieces (the bulk is directed towards center). Sew shoulder seams, press towards back, serge.

4. Sew the seam of the stand collar, press the seam apart. Sew the stand collar into neckline, slashing corners, press seam allowances at stand collar. Snip into seam allowance near the mark of the slit on the neckline. Sew center front seam. Serge the seam allowances and press towards left.

5.Snip into seam allowance near the mark of the slit of the neckline on the front neckline facings. Sew center edge facings. Press the seam apart.

6. Sew the seam of the stand collar on the front neckline facing, press the seam apart. Sew shoulder seam on front neckline facing and back neckline facing, press the seam apart. Serge the outer edge. Sew the stand collar into neckline of facings, press towards top. Pin facings to garment right sides together and sew the edges of the neckline and of the stand collar. Clip into curves, turn the facings onto the wrong side and press. Slip stitch the seams of the stand collars together. Sew by hand the shoulder seams of the facing to the shoulder seams of the garment.

7. Sew side seams, press towards the back, serge.

8. Serge the sleeve edges separately. Sew sleeve seam from armhole up to mark for slit, press the seam apart. Topstitch slit at 0.1 cm from fold. Sew a gathering stitch along lower edge of sleeve and gather fullness. Sew sleeves into armholes, serge and press.

9. Fold cuffs in half lengthwise right sides together and sew side edges. Start and stop stitching exactly at the marked line of the cuff seam. Turn the piece right side out, press. Sew outer side of cuff to sleeve, fold the seam allowance of the inner cuff inward and stitch in the seam attaching the outer cuff.

10. Press lower edge of garment onto wrong side at 1 cm, then at 1 cm and topstitch.

11. Make buttonholes and sew on buttons onto cuffs.

Технический рисунок:

