

Top With V-Shaped Yoke - Выкройка #2718

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing.

Seam allowances: seam allowance for hem of garment - 2 cm.
Other seams - 1.0 cm.


О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 2
3. Front yoke - cut 2

Fusible interfacing:

1. Front yoke - cut 1

Инструкции:

1. Apply fusible interfacing to the yoke.
2. Pin pieces together yokes right sides together and sew the neckline. Clip seam allowances, turn the piece right side out, straighten, press.
3. Sew a gathering stitch along the upper edge of front and gather fullness. Sew center seam on front, press towards left and serge. Sew yoke to front, slashing corners, press seam allowances onto front and serge.
4. Sew shoulder seams (the shoulder edge of the back is longer than the shoulder edge of the front by the width of the seam allowance), press towards the back and serge. Cut (or take ready) bias tape, its width should equal 4 cm and length should equal the length of back neckline + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to neckline from the right side, leaving loose ends, and sew. Fold bias tape onto wrong side, clip into seam allowances and topstitch onto main piece along the fold. Press seam.
5. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape onto armhole edge from the right side and sew, fold the bias tape onto wrong side and topstitch onto main piece along the fold.
6. Sew side seams, press towards the back and serge.
7. Serge the lower edge of garment, press onto wrong side and topstitch.

Технический рисунок:

