

Dress With Flared Skirt - Выкройка #2779

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; dress zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of garment – 2 cm.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Lower center back – cut 1
4. Center front - cut 2
5. Side front - cut 2
6. Lower center front – cut 1
7. Lower side part – cut 2

8. Sleeve - cut 2
9. Back neck facing - cut 4
10. Front neck facing - cut 2
11. Cuff - cut 2

Fusible interfacing:

1. Back neck facing - cut 2
2. Front neck facing - cut 1
3. Cuff - cut 2

Инструкции:

1. Apply fusible interfacing.
2. Serge center back edges separately on each piece. Sew outer part of back neckline facing to back. Press towards facings. Sew center back seam from marking for zipper to lower edge, press the seam apart. Sew in zipper. Sew lower back to garment, serge and press towards bottom.
3. Sew center front seam. Serge the seam allowances and press towards left. Sew lower front, serge and press towards bottom. Sew the outer facing into the front neckline. Clip seam allowances and press towards facing.
4. Sew side seams, press towards the back and serge. Sew lower fronts to upper fronts and sew lower backs to upper backs, serge seams and press towards top.
5. Sew side backs to center back. Sew side fronts to center front, press seam allowances towards center, serge.
6. Sew shoulder seams. Serge seams and press towards back.
7. Sew shoulder seams on inner facings. Press the seam apart. Serge the outer edge. Pin facing on garment, right sides together and sew the neckline opening. Clip seam allowances, fold facings onto wrong side and press. Pin the seam allowance of inner facing to the seam of outer facing and stitch-in-the-ditch .
8. Sew sleeve seam, press towards back and serge. Sew cuff into a ring. Press the seam apart. Fold cuff in half lengthwise right side out and press. Sew cuff to lower edge of sleeve from the right side. Serge. Fold the cuff onto the sleeve and press. Sew sleeves into armholes, serge and press.
9. Serge bottom edge of dress, press onto wrong side and topstitch.

Технический рисунок:

