

Safari Dress - Выкройка #2821

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 16 buttons; buckle.

Seam allowances: all seams – 1 cm. Seam allowance for hem 2 cm, upper seam allowance of pocket – 2 cm.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Back - cut 1 on fold
2. Back yoke - cut 1 on fold
3. Front yoke - cut 2
4. Front - cut 2
5. Stand collar - cut 2
6. Pocket - cut 2
7. Flap - cut 4

8. Placket – cut 2
9. Belt Loop – cut 1
10. Decorative Tab – cut 2
11. Cuff – cut 2
12. Belt – cut 1 on fold

Fusible interfacing:

1. Belt – cut 1 on fold
2. Stand collar – cut 1
3. Flap – cut 2
4. Placket – cut 2
5. Cuff – cut 2
6. Decorative Tab – cut 2

Инструкции:

1. Apply fusible interfacing.
2. Sew back yoke to back. Serge the seam allowances and press onto yoke. Sew a decorative stitchline at 0.2 and 0.5 from seam.
3. Pin the pocket flaps together pairwise, right sides together and sew the side and the lower edges. Trim seam allowances, turn right side out and press. Sew decorative stitch lines along the lower edge and along the side edges. Make buttonholes.
4. Make and baste a box pleat on the pocket. Fix the folds of the pleat with decorative stitch lines at 0.2 cm from the fold. Serge the upper edges of the pocket. Fold the upper seam allowances onto the wrong side, topstitch and press. Serge the lower and the side seam allowances of the pocket. Fold the lower and the side seam allowances onto the wrong side, press and press. Topstitch the pocket onto front with two parallel stitch lines. Sew front yoke to front, inserting flap. Serge seams and press towards top. Sew a decorative stitchline at 0.2 and 0.5 cm from seam.
5. Sew outer edge of placket to front. Press the seam allowance at placket. Fold placket onto wrong side, fold inside the open edge and topstitch from the right side at 0.2 cm from fold. Sew parallel decorative stitch lines along the placket.
6. Sew shoulder seams, press towards the back and serge.
7. Pin together parts of stand collar, right sides together and sew upper edge. Trim seam allowances, turn right side out and press. Sew the upper stand collar into the neckline of garment. Fold the seam allowance of the lower stand collar onto wrong side and stitch-in-the-ditch along seam of upper one stand collars. Sew parallel decorative stitch lines.

9. Sew side seams, processing the sleeve seam at the same time. Press seams towards back and serge.
9. Sew cuff into a ring. Press the seam apart. Fold cuff in half lengthwise and press. Sew outer side of cuff to sleeve, fold under the seam allowance of the inner side onto wrong side and topstitch into the seam of the outer cuff.
10. Fold tab in half lengthwise right sides together and sew longer and one shorter edge. Trim seam allowances, turn right side out and press. Sew decorative stitch lines along the finished sides. Make buttonholes. Fold inside the unsewn edge and topstitch the tab onto the wrong side of the sleeve according to the markings.
11. Fold belt loop in half lengthwise right sides together and sew along long side. Then turn right side out, straighten the seam, placing it on the fold, and press. Sew parallel stitch lines at 0.2 cm from the folds. Cut the belt loops.
12. Fold belt in half lengthwise, right sides together, cut off the pointed end from one of the sides. Sew the belt along two shorter and one longer sides, leaving an opening for turning. Trim away corners, turn right side out belt, sew the opening closed. Sew parallel decorative stitch lines around all edges of belt. Thread in the decorative buckle and fix it in place by sewing by hand.
13. Adjust the position of the belt loops. Topstitch the belt loops onto the side seam and onto center back.
14. Seam allowance for hem serge, press onto wrong side and topstitch.
15. Make buttonholes and sew on buttons.

Технический рисунок:

